

PyXspec  
0.9 Beta

Generated by Doxygen 1.7.3

Wed Jul 20 2011 15:35:24

# Contents

<b>1</b>	<b>PyXspec Documentation</b>	<b>1</b>
1.1	Introduction	1
1.2	About This Manual	2
1.3	Authors	2
<b>2</b>	<b>Build and Install PyXspec</b>	<b>2</b>
2.1	Requirements	2
2.2	Building/Installing	2
2.3	Running on Mac OS X	3
2.4	Troubleshooting	4
<b>3</b>	<b>A Tutorial - Quick Version</b>	<b>5</b>
3.1	Jumping In - The Really Quick Version	5
3.2	Terminology	6
3.3	Getting Help	6
3.4	The 6 Global Objects	6
3.5	Loading And Removing Data	7
3.6	Defining Models	8
3.6.1	Component and Parameter Objects	9
3.6.2	Setting Multiple Parameters	10
3.7	Fitting	11
3.8	Plotting	12
<b>4</b>	<b>A Tutorial - Extended Version</b>	<b>13</b>
4.1	Contents	13
4.2	Data	14
4.2.1	Background, Response, and Arf	14
4.2.2	Ignore/Notice	16
4.3	Models	17
4.3.1	Model With Multiple Data Groups	17
4.3.2	Defining Multiple Models	17
4.3.3	Component And Parameter Access Part 2	19
4.3.4	Flux Calculations	19
4.3.5	Local Models	20
4.4	Fitting	20
4.4.1	Error	20
4.4.2	Query	21
4.4.3	Steppar	21
4.5	Fakeit	21
4.5.1	From Existing Spectra	22
4.5.2	From Scratch	22
4.5.3	FakeitSettings Objects	22
4.5.4	OGIP Type-2 Files	23
4.6	Monte Carlo Markov Chains (MCMC)	24

4.7	Plotting	26
4.8	XSPEC Settings	26
4.9	Logging And XSPEC Output	27
4.10	Exceptions And Error Handling	28
4.11	Adding Attributes To PyXspec Objects	28
4.12	Using With Other Packages	29
<b>5</b>	<b>What's Missing</b>	<b>30</b>
<b>6</b>	<b>Class Index</b>	<b>31</b>
6.1	Class List	31
<b>7</b>	<b>Class Documentation</b>	<b>31</b>
7.1	Background Class Reference	31
7.1.1	Detailed Description	32
7.1.2	Constructor & Destructor Documentation	32
7.1.3	Member Data Documentation	33
7.2	Chain Class Reference	34
7.2.1	Detailed Description	35
7.2.2	Constructor & Destructor Documentation	35
7.2.3	Member Function Documentation	36
7.2.4	Member Data Documentation	36
7.3	ChainManager Class Reference	38
7.3.1	Detailed Description	38
7.3.2	Constructor & Destructor Documentation	39
7.3.3	Member Function Documentation	39
7.3.4	Member Data Documentation	41
7.4	Component Class Reference	42
7.4.1	Detailed Description	42
7.4.2	Constructor & Destructor Documentation	42
7.4.3	Member Function Documentation	43
7.4.4	Member Data Documentation	43
7.5	DataManager Class Reference	43
7.5.1	Detailed Description	44
7.5.2	Constructor & Destructor Documentation	44
7.5.3	Member Function Documentation	44
7.5.4	Member Data Documentation	49
7.6	FakeitSettings Class Reference	49
7.6.1	Detailed Description	50
7.6.2	Constructor & Destructor Documentation	51
7.6.3	Member Data Documentation	52
7.7	FitManager Class Reference	53
7.7.1	Detailed Description	55
7.7.2	Constructor & Destructor Documentation	56
7.7.3	Member Function Documentation	56
7.7.4	Member Data Documentation	59

7.8	Model Class Reference	61
7.8.1	Detailed Description	62
7.8.2	Constructor & Destructor Documentation	63
7.8.3	Member Function Documentation	64
7.8.4	Member Data Documentation	67
7.9	ModelManager Class Reference	68
7.9.1	Detailed Description	68
7.9.2	Constructor & Destructor Documentation	69
7.9.3	Member Function Documentation	69
7.9.4	Member Data Documentation	74
7.10	Parameter Class Reference	74
7.10.1	Detailed Description	75
7.10.2	Constructor & Destructor Documentation	76
7.10.3	Member Function Documentation	76
7.10.4	Member Data Documentation	77
7.11	PlotManager Class Reference	79
7.11.1	Detailed Description	80
7.11.2	Constructor & Destructor Documentation	82
7.11.3	Member Function Documentation	82
7.11.4	Member Data Documentation	86
7.12	Response Class Reference	88
7.12.1	Detailed Description	89
7.12.2	Constructor & Destructor Documentation	89
7.12.3	Member Data Documentation	89
7.13	Spectrum Class Reference	90
7.13.1	Detailed Description	92
7.13.2	Constructor & Destructor Documentation	94
7.13.3	Member Function Documentation	95
7.13.4	Member Data Documentation	97
7.14	XspecSettings Class Reference	101
7.14.1	Detailed Description	102
7.14.2	Constructor & Destructor Documentation	104
7.14.3	Member Function Documentation	104
7.14.4	Member Data Documentation	105

## 1 PyXspec Documentation

The source code distribution of XSPEC is required for using PyXspec

### 1.1 Introduction

PyXspec is an object oriented Python interface to the XSPEC spectral-fitting program. It provides an alternative to Tcl, the sole scripting language for standard Xspec usage.

With PyXspec loaded, a user can run Xspec with Python language scripts or interactively at a Python shell prompt.

At this early release stage, not all of the full standard Xspec functionality has been implemented (see [What's Missing](#)). However we will continue to add to this, and we look forward to hearing users' comments and suggestions to help us prioritize the future work.

## 1.2 About This Manual

The manual contains a [Build/Install and Troubleshoot](#) section, a [Quick Version](#) tutorial showing basic PyXspec usage, and an [Extended Version](#) tutorial for greater functionality. The [Quick Version](#) is the recommended starting point for all users.

A class reference guide follows, with descriptions for each of the PyXspec public class methods and attributes. The guide is auto-generated by Doxygen directly from the PyXspec Python code files.

## 1.3 Authors

PyXspec was developed by Craig Gordon and Keith Arnaud

HEASARC Software Development, Astrophysics Science Division,

Code 660.1, NASA/GSFC, Greenbelt MD 20771

Please send questions, comments, and bug reports to [xspec12@athena.gsfc.nasa.gov](mailto:xspec12@athena.gsfc.nasa.gov)

# 2 Build and Install PyXspec

## 2.1 Requirements

Since we do not distribute Python with the HEASOFT packages, you'll need to have it already installed on your system (which it is with most Linux and Mac OSX distributions). PyXspec requires a Python version from **2.3** or later. The **python** executable must be on your path, and with the library and header files located in the standard directories relative to the executable (see the **Troubleshooting** section for more info).

## 2.2 Building/Installing

PyXspec is fully integrated into the general HEASOFT build procedure, as described at <http://heasarc.gsfc.nasa.gov/heasoft/install.html> . So it will

be **built and installed automatically** with the rest of XSPEC/HEASOFT, requiring no additional effort from the user.

Once HEASOFT is finished building and installing, you should find PyXspec's code files and lib\_pyXspec.so library in the directory \$HEADAS/lib/python/xspec.

When you run the HEASOFT initialization script (\$HEADAS/headas-init.csh or .sh), it will add \$HEADAS/lib/python to your PYTHONPATH environment. This allows Python find the PyXspec module so that you may load it into your session from anywhere, using the "import xspec" statement.

## 2.3 Running on Mac OS X

These issues apply only to Mac OS X users. Linux users may skip this section.

**Case 1:** Running the default **Xcode** distribution of Python (normally /usr/bin/python).

You may use the default Xcode Python if your HEASOFT distribution was built using the **Xcode gcc and g++ compilers**, with only the Fortran compiler coming from a 3rd party such as Fink or MacPorts. But if you built HEASOFT with ALL of your compilers coming from Fink or MacPorts, you cannot use the Xcode Python (see **Case 3**).

If your platform is **OS X Snow Leopard** or later, you must set:

```
export VERSIONER_PYTHON_PREFER_32_BIT=yes      # Bourne-like shells
or
setenv VERSIONER_PYTHON_PREFER_32_BIT yes      # C-like shells
```

BEFORE importing the xspec module into Python.

**Case 2:** Running a Python distribution obtained from **www.python.org**.

If you're using a recent distribution from www.python.org (Python 2.7 or later) on **Snow Leopard**, you'll need to ensure that you run the 32-bit version, and the method used in **Case 1** will not work. Instead, invoke 32-bit Python by way of the **arch** command. For example:

```
arch -i386 python2.7
```

**Case 3:** Running the **Fink** or **MacPorts** Python.

This applies only to users who have built HEASOFT using Fink or MacPorts for **ALL 3 of their compilers** (gcc, g++, gfortran). Note that you can avoid all of this if you build HEASOFT using Mac's own Xcode gcc and g++, and only use Fink or MacPorts for gfortran.

You are going to have to get the corresponding Fink or MacPorts distribution of Python for both building and running PyXspec. The standard Xcode Python (in /usr/bin) will conflict with libraries pulled in by the Fink and MacPorts gcc.

To rebuild PyXspec using the Fink or MacPorts Python, first edit the file `heasoft-<ver>/Xspec/src/XSUser/Python/xspec/Makefile` by adding definitions for `PYTHON_INC` and `PYTHON_LIB` that point to your Fink or Mac Python header and library files. For example if using the Fink Python v2.6 in its default location, you would insert the following in your Makefile, after the definition for `HD_LIBRARY_ROOT` and before the definition for `HD_CXXFLAGS`:

```
PYTHON_INC = /sw/include/python2.6
PYTHON_LIB = -L/sw/lib/python2.6/config # Note that this must
begin with '-L'
```

Then from the same directory containing the Makefile, do:

```
hmake clean
hmake
hmake install
```

## 2.4 Troubleshooting

If the HEASOFT configuration stage fails when it's processing PyXspec, it will just issue a warning and continue. Its failure should not affect the rest of the XSPEC and HEASOFT build. Standard XSPEC will still be fully functional, but its Python interface won't be available.

The most likely cause of a PyXspec build failure is that the HEASOFT configuration script can't find a **python** executable and/or its accompanying library and header files. You should first check that the command "which python" can find an executable on your path. The configuration script first looks for **python**, which is normally a symbolic link to the version-specific executable. If it doesn't find that, it looks for **python2.7** down to **python2.3** in descending order.

Once it's found an executable, it looks for `Python.h` and `libpython[m.n].so` (or `.dylib`) in the directories `../include/python[m.n]` and `../lib` respectively, relative to the executable location. The configuration fails if either file is missing.

If you are running on **Mac OS X Snow Leopard** and get a Python "ImportError" message containing such statements as **no suitable image found** and **mach-o, but wrong architecture**, you need to ensure that you are running the 32-bit version of Python. See **Case 1** and **Case 2** in the previous section for how to do this.

If you are running on a **Mac** and have built your HEASOFT installation with **all 3 compilers (gcc, g++, gfortran)** coming from **Fink** or **MacPorts**, AND you get a runtime error that begins with something like:

```
python(86419) malloc: *** error for object 0x574b160: pointer
being freed was not allocated
```

then it likely means there's a conflict between your default Python distribution and the

compiler libraries used to build PyXspec. Please see **Case 3** in the previous section for how to rebuild PyXspec with a Fink or MacPort distribution of Python.

### 3 A Tutorial - Quick Version

This assumes the user already has a basic familiarity with both XSPEC and Python. Everything in PyXspec is accessible by importing the package **xspec** into your Python script.

**Mac OS X Snow Leopard users:** Did you remember to make sure you're running the 32-bit version of Python, as shown in the [Running on Mac OS X](#) section of the "Build and Install" page?

PyXspec can be utilized in a Python script or from the command line of the plain interactive Python interpreter. PyXspec does not implement its own command handler, so it is NOT intended to be run as the Python equivalent of a traditional interactive XSPEC session (which is really an *enhanced* interactive Tcl interpreter). In other words you launch an interactive PyXspec session with:

```
UNIX>python
>>> import xspec
>>>
```

rather than:

```
UNIX>xspec
XSPEC12>
```

Note that in all the tutorial examples the **xspec** package name qualifier is left off. You must either include the **xspec** qualifier:

```
s = xspec.Spectrum("file1.pha")
```

or use a variation of the Python import or from...import commands:

```
from xspec import *
s = Spectrum("file1.pha")
```

#### 3.1 Jumping In - The Really Quick Version

A simple Xspec load-fit-plot Python script may look something like this:

```
#!/usr/bin/python
from xspec import *
Spectrum("file1.pha")
```



```
Model("wabs*pow")
Fit.perform()
Plot.device = "/xs"
Plot("data")
```

Keeping this template in mind, we'll proceed to fill in the details...

## 3.2 Terminology

This description uses the standard Python object-oriented terminology, distinguishing between **classes** and *objects*. **Class** is used when referring to the *type* or definition of an *object*. An *object* refers to a specific instance of a **class** and is normally assigned to a variable. For example a user may load 3 data files by creating 3 spectral data objects *s1*, *s2*, and *s3*, which are all instances of the class **Spectrum**.

The functions and stored data members that make up the definition of a **class** are referred to as **methods** and **attributes** respectively.

The term **Standard XSPEC** refers to the traditional ways of using XSPEC, either with a Tcl script or an interactive XSPEC session.

## 3.3 Getting Help

There are two ways to get help for programming with PyXspec classes. The first is by viewing the **Classes** section of this manual. The **Classes:Class List** subsection is particularly useful as an entry point, as it contains hyperlinks to descriptions of every PyXspec class that is part of the public interface. The second way is to call Python's built-in **help([class])** function from the interactive Python shell. Both methods will display essentially the same information, which originates in the class **docstrings** in the code files.

## 3.4 The 6 Global Objects

An XSPEC session fundamentally consists of loading data, fitting that data to a model, and plotting the results. To manage these operations, PyXspec offers the user 6 global objects: *AllChains*, *AllData*, *AllModels*, *Fit*, *Plot*, and *Xset*. Note that these are NOT the names of classes. They are instantiated *objects* of the **class** types shown in Table 1.

PyXspec instantiates these objects immediately upon the importing of the **xspec** package. You cannot create any other objects of these class types, as they each allow only 1 instance of their type. (They are **singletons** in the language of design patterns.)

Operations involving these should ALWAYS be performed through the objects and NOT their class names. These class names should never appear in your code.

Object Name	Class	Role
<i>AllChains</i>	<b>ChainManager</b>	Monte Carlo Markov Chain container
<i>AllData</i>	<b>DataManager</b>	Container for all loaded data sets (objects of class <b>Spectrum</b> )
<i>AllModels</i>	<b>ModelManager</b>	Container for all <b>Model</b> objects
<i>Fit</i>	<b>FitManager</b>	Manager class for setting properties and running a fit
<i>Plot</i>	<b>PlotManager</b>	Manager class for performing XSPEC plots
<i>Xset</i>	<b>XspecSettings</b>	Storage class for Xspec settings

Table 1: Table 1. PyXspec global objects

### 3.5 Loading And Removing Data

Spectral data files can be loaded in several ways. You can create an object of the **Spectrum** class by passing it the data file name:

```
s1 = Spectrum("file1.pha")
```

which also adds the new object *s1* to the *AllData* container. Or you can simply add the new file directly to the container without retrieving a **Spectrum** object:

```
AllData += "file1.pha"
```

Later you can always obtain a **Spectrum** object reference to any of the loaded spectra by passing *AllData* an integer:

```
s2 = AllData(2) # s2 is a reference to the 2nd loaded spectrum
```

For more complicated data loading, you have access to the same functionality in Standard XSPEC's **data** command. Simply pass a string to the *AllData* object's `__call__` method:

```
AllData("file1 file2 2:3 file3")
```

Note that only the last example allows you to assign multiple data groups, the 3rd spectrum being assigned to data group 2. Also note that in the last example any previously loaded data sets are removed, thus reproducing the behavior of Standard XSPEC's **data** command.

Other ways of removing Spectrum objects (ie. data sets) from the container:

```
AllData -= 3 # Removes the 3rd Spectrum object (the spectrum with index number 3) from the container.
```

```
AllData -= s1 # Removes the Spectrum object s1.
```

```
AllData -= "*" # Removes all Spectrum objects.
```

```
AllData.clear() # Removes all Spectrum objects.
```

You can check the current state of the *AllData* container at any time by doing:

```
AllData.show()
```

Similarly, to view information about a single **Spectrum** object:

```
s2.show()
```

### 3.6 Defining Models

The basic way of defining an XSPEC model is to create an object of the PyXspec class **Model**. Simply pass in a string containing a combination of 1 or more XSPEC model **components**. Since this uses the same syntax as Standard XSPEC's **model** command, component abbreviations are allowed:

```
m1 = Model("wa*po + ga")
```

and to see a complete listing of available XSPEC model components, do:

```
Model.showList()
```

When you define a model like this, PyXspec also automatically adds the new object to the global *AllModels* container. If the model is applied to multiple data groups, object copies are added to the container for each data group.

Similar to the case of spectral data, you can also load models directly into the global container:

```
# Another way to define a new model and create an object for
each data group.
```

```
AllModels += "wa*po + ga"
```

```
# Retrieve the model object assigned to data group 2.
```

```
m2 = AllModels(2)
```

```
# Various ways to remove all model objects from the container.
```

```
AllModels.clear()
```

```
AllModels -= "*"

```

To display models and their parameters:

```
# This displays all parameters in all model objects:
```

```
AllModels.show()
```

```
# While this displays just parameters 1,2,3 and 5:
```

```
AllModels.show("1-3, 5")  
  
# This displays a single model object:  
  
m2.show()
```

For defining multiple (or named) models and assigning multiple sources, please see the [Extended Tutorial](#) section.

### 3.6.1 Component and Parameter Objects

Model objects contain **Component** objects and **Component** objects contain **Parameter** objects. There are several ways to access and set components and parameters individually (and if you want to change many parameter values at once, it may be faster to use the Model object's **setPars** method described in the next section). Examples of individual Component and Parameter object access:

```
# Component objects are accessible-by-name as Model object  
attributes*:  
  
comp1 = m1.wabs  
comp2 = m1.powerlaw  
  
# Parameter objects are accessible-by-name as Component object  
attributes:  
  
par4 = m1.gaussian.LineE  
  
# ...and we can modify their values:  
  
par4.values = 3.895  
m1.wabs.nH = 5.0  
comp2.PhoIndex = 1.5  
  
# Can also get a Parameter object directly from a Model, without  
going through a Component.  
  
# Just pass the Model the Parameter index number:  
  
par5 = m1(5)  
  
# Examples of numerical operations allowed with Parameter objects:  
  
par4 += 0.75  
par4 *= 2.0  
  
y1 = m1.wabs.nH*100.0  
y2 = par4 + par5
```

(\*)For models with duplicate copies of components, see the [Extended Tutorial](#) for accessing Component objects by name.

Note that in the above examples, only the parameter's *value* is being accessed or modified. To change all or part of its FULL list of settings including auxiliary values: *value*, *fit delta*, *min*, *bot*, *top*, *max*, you can set its **values** attribute to a tuple or list of size 1-6:

```
par4.values = 4.3, .01, 1e-3
par4.values = [4.3, .01, 1e-3, 1e-2, 100, 200]
```

Or for greater flexibility you can set it to a string using Standard XSPEC's **newpar** command syntax:

```
# This allows you to set new values non-consecutively.
par4.values = "1.0, -.01,,,150"
```

A quick way to freeze or thaw a parameter is to toggle its **frozen** attribute:

```
par4.frozen = False
par5.frozen = True
```

To link a parameter to one or more others, set its **link** attribute to a link expression string as you would have with the **newpar** command. To remove the link, set **link** to an empty string or call the parameter's **untie** method.

```
par5.link = "2.3 * 4" # Link par 5 to par 4 with a multiplicative
                        # constant.
par5.link = "" # Removes the link.
par5.untie() # Also removes the link.
```

Also ALL linked parameters in a model object can be untied with a single call to the **Model** class **untie** method.

To display a parameter's full set of values (including auxiliary values), just print its **values** attribute:

```
>>> print par4.values
[6.5, 0.05, 0.0, 0.0, 1000000.0, 1000000.0]
>>>
```

### 3.6.2 Setting Multiple Parameters

\*\*\* This section is valid only for XSPEC patched to 12.7.0f or later \*\*\*

You can set multiple parameter values with a single call to the **Model** object's **setPars** method. This may be considerably faster than setting parameters one at a time through the individual **Parameter** objects as shown in the previous section. With **setPars**, the model will be recalculated just ONCE after all the changes have been made. But when setting through individual **Parameter** objects, the model must be recalculated after EACH parameter change.

```

# For Model object m1, supply 1 or more new parameter values
in consecutive order:

m1.setPars(2.5, 1.4, 1.0e3) # This changes pars 1, 2, and 3.

# Can also change parameter auxiliary values by passing a string
using the same

# syntax as with Standard XSPEC's newpar command:
m1.setPars(.95, "1.8,-5,-4,10,10")

# Now set parameters NON-CONSECUTIVELY.

# Pass keywords with p[n] notation to skip over some parameters.
# [n] is the 1-based parameter index number.

# This example changes pars 1, 2, 4, and 6:
m1.setPars(.95, 1.2, p4="10.0,,,1e4,1e5", p6=2.0)

Parameters can also be set by passing values as additional keyword arguments to the
Model object constructor. You do this the same way as with the setPars method, except
that here you MUST ALWAYS include the p[n] keywords:

# Supply values for parameters 1 and 3, use defaults for the
rest.

m = Model("wa*ga", p1=1.5, p3=.2)

# This example is WRONG! Without p[n] keywords, the values
are mistaken for

# other Model constructor arguments.
m = Model("wa*ga", 1.5, .9) # Bad!

*** End section requiring patch 12.7.0f ***

```

### 3.7 Fitting

Once data and models are loaded, fitting is performed by calling the **perform** method of the *Fit* global object:

```
Fit.perform()
```

Some of the more frequently modified fit settings are the type of statistic to minimize and the maximum number of fit iterations to perform. These settings are attributes of *Fit*:

```

Fit.nIterations = 100
Fit.statMethod = "cstat"
Fit.statMethod = "chi"

```

Please see the class reference guide and the [Extended Tutorial](#) for *Fit*'s complete functionality.

To display the fit results at any time:

```
Fit.show()
```

### 3.8 Plotting

In Standard XSPEC, plot settings are adjusted using the **setplot** command while the plot is displayed through the **plot** command. In PyXspec, all plot settings and functionality is handled through the global *Plot* object. A device must be set before any plots can be displayed, and this done through the **device** attribute:

```
Plot.device = "/xs"
```

The device can also be set to print to an output file in several formats. The list of possible devices is given by the **cpd** command in the Standard XSPEC manual.

A typical setting to adjust is the X-axis units. You can choose to plot channel numbers, or select from various energy and wavelength units. The strings can also be abbreviated. Examples:

```
Plot.xAxis = "channel"
```

```
Plot.xAxis = "MeV"
```

```
Plot.xAxis = "Hz"
```

```
Plot.xAxis = "angstrom"
```

The displays of individual additive components or background spectra is toggled by setting their attributes to a bool:

```
Plot.add = True
```

```
Plot.background = False
```

Similarly log/linear settings for data plots (when using energy or wavelength units):

```
Plot.xLog = True
```

```
Plot.yLog = False
```

The current plot settings are displayed with:

```
Plot.show()
```

To actually display a plot, send 1 or more string arguments to the *Plot* `__call__` method:

```
# Single panel plots
```

```
Plot("data")
```

```
Plot("model")
```

```
Plot("ufspec")
# Multi panel plots
Plot("data chisq")
Plot("data", "model", "resid")
# Call Plot with no arguments to repeat the previously entered
Plot command
Plot()
```

After displaying a plot, you can get an array of the plotted values by calling one of Plot's retrieval methods. All of these functions take an optional plot group number argument for the case of multiple plot groups, and all return the plot values in a Python list.

```
Plot("data")
xVals = Plot.x()
yVals = Plot.y()
yVals2 = Plot.y(2) # Gets values for data in the second plot
group
modVals = Plot.model()
# To get a background array, Plot.background must be set prior
to plot
Plot.background = True
Plot("data")
bkg = Plot.backgroundVals()
# Retrieve error arrays
xErrs = Plot.xErr()
yErrs = Plot.yErr()
```

## 4 A Tutorial - Extended Version

This assumes the user is familiar with the basics of PyXspec as explained in the Quick Tutorial.

### 4.1 Contents

- [Data](#)



- Background, Response, and Arf
  - Ignore/Notice
- Models
  - Model With Multiple Data Groups
  - Defining Multiple Models
  - Component And Parameter Access Part 2
  - Flux Calculations
  - Local Models
- Fitting
  - Error
  - Query
  - Steppar
- Fakeit
  - From Existing Spectra
  - From Scratch
  - FakeitSettings Objects
  - OGIP Type-2 Files
- Monte Carlo Markov Chains (MCMC)
- Plotting
- XSPEC Settings
- Logging And XSPEC Output
- Exceptions And Error Handling
- Adding Attributes To PyXspec Objects
- Using With Other Packages

## 4.2 Data

### 4.2.1 Background, Response, and Arf

When a **Spectrum** object is created from a spectral data file, PyXspec also reads the file's BACKFILE, RESPFILE, and ANCRFILE keywords and will load the corresponding background, response, and arf files. The spectrum's **Background** and **Response** objects are then available as attributes of the **Spectrum** class, while the arf file name becomes an attribute of the **Response** class:

```
s1 = Spectrum("file1")
b1 = s1.background
r1 = s1.response
arfFileName = r1.arf
```

Note that you never create **Background** and **Response** objects directly. They are accessible only through the **Spectrum** class attributes.

These attributes may also be used to add, change, or remove auxiliary files to an existing **Spectrum** object:

```
# Add or replace files:
s1.background = "newBackground.pha"
s1.response.arf = "newArf.pha"

# Removal examples:
s1.response = None
s1.background = ""
```

**Background** and **Spectrum** store their original file names in their **fileName** attribute. This means that while you SET the `Spectrum.background` object by assigning it a file name (as shown above), to GET the file name you must access its **fileName** attribute:

```
bkgFileName = s1.background # Wrong!!! This returns the entire
                             # Background object, not a string.
bkgFileName = s1.background.fileName # Correct
```

**Response** stores its RMF and optional ARF file names in its **rmf** and **arf** attributes respectively:

```
rmfFileName = r1.rmf
arfFileName = r1.arf
```

**Background** objects have some of the same attributes as **Spectrum** objects, such as **areaScale**, **exposure**, **energies**, and **values**. The **Spectrum** object's **values** array (actually a tuple) does NOT include contributions from the background. Those are stored separately in the associated **Background** object. Please see the **Classes** reference guide or call the Python help function for the full class descriptions.

The **Spectrum** class also provides a **multiresponse** array attribute for assigning multiple detectors (or sources) to a spectrum. The standard 0-based Python array indices corresponding to the 1-based XSPEC source numbers:

```
# Set a response for source 2
s1.multiresponse[1] = "resp2.rsp"
# Get the response object for source 2
```

```
r2 = s1.multiresponse[1]
# Remove the response from source 2
s1.multiresponse[1] = None
# This is the same as doing s1.response = "resp1.rsp"
s1.multiresponse[0] = "resp1.rsp"
```

The rule is: when doing single-source analysis (typical of most XSPEC sessions) use the **response** attribute, otherwise use the **multiresponse** array.

#### 4.2.2 Ignore/Notice

To ignore channels for a SINGLE spectrum, call the **Spectrum** object's **ignore** method passing a string following the same syntax as for Standard XSPEC's **ignore** command:

```
s1.ignore("20-30 50-**")
s1.ignore("**-5")
```

Similarly, to notice channels in a single spectrum:

```
s1.notice("10-30, 80-**")
s1.notice("all")
```

As with Standard XSPEC, if the **x-axis** plot units are set to energies or wavelengths, **ignore** and **notice** will accept floating-point input assumed to be in those same units:

```
Plot.xAxis = "nm"
# Ignore channel bins corresponding to 15.0 to 20.0 nm wavelengths:
s1.ignore("15.-20.")
```

The currently noticed channel ranges are displayed for each spectrum in the `AllData.show()` output. You can also get a list of the individual noticed channel numbers from **Spectrum**'s **noticed** attribute:

```
>>> s1.noticed
[3, 4, 5, 7, 8, 10]
```

To apply **ignore** and **notice** commands to ALL loaded spectra, call the methods from the global *AllData* object. To apply to a subset of loaded spectra, add a range specifier to the left of the colon:

```
# These apply to all loaded spectra
AllData.ignore("100-120, 150-200")
AllData.notice("all")
AllData.ignore("bad")
```

```
# These apply to a subset of loaded spectra
AllData.ignore("1-3: 60-65")
AllData.notice("2-**:50-60")
```

## 4.3 Models

### 4.3.1 Model With Multiple Data Groups

When a model is defined and spectra are assigned to multiple data groups, PyXspec will generate a **Model** object copy for each data group (assuming the spectra also have responses attached). So if:

```
m1 = Model("wa*ga")
AllData("file1 2:2 file2")
```

then there are 2 **Model** objects for the model definition `wabs*gaussian`. The variable `m1` is set to the object belonging to data group 1, and to get the object for data group 2 do:

```
m2 = AllModels(2)
```

`m1` and `m2` will each have the same set of **Component** and **Parameter** objects. However `m1`'s parameters are indexed from 1-4 while `m2`'s are from 5-8. (This is obvious from the output of `AllModels.show()`.) So:

```
p = m1(5) # Error!
p = m2(5) # OK
```

PyXspec also provides a couple of **Model** attributes to help the user keep track of parameter indexing:

```
>>> m1.startParIndex
1
>>> m2.startParIndex
5
>>> m1.nParameters
4
```

### 4.3.2 Defining Multiple Models

Beginning with XSPEC12, it became possible to assign multiple sources to spectra, and each source may have its own model function definition. To keep track of multiple model definitions, XSPEC requires that you assign them names. In PyXspec, the model

name and source number are supplied as additional arguments to the **Model** `__init__` function:

```
# Define a model named "alpha" assigned to source 1
m_1_1 = Model("wa*po", "alpha")
# Define a model named "beta" assigned to source 2
m_2_1 = Model("const*bbody", "beta", 2)
# (In both of these cases, the returned object belongs to data
group 1)
```

Note that in all previous examples in this tutorial, we have been using unnamed models which were assigned to source 1. Named models and source numbers may also be defined directly into the *AllModels* container by passing in a tuple:

```
# Define a model named "defn1" assigned to source 1
AllModels += ("wa*po", "defn1")
# Define a model named "defn2" assigned to source 2
AllModels += ("const*bbody", "defn2", 2)
# This replaces "defn1" with an unnamed model for source 1
AllModels += "wa*gaussian"
```

and from which **Model** objects can be retrieved:

```
# Get the "defn2" Model object for data group 1
m_2_1 = AllModels(1, "defn2")
# ...and for data group 2
m_2_2 = AllModels(2, "defn2")
```

[As with Standard XSPEC, to define a model for source numbers > 1 you first must load a detector response for the source. See "Background, Response, and Arf" in the previous section.] To remove model definitions:

```
# Remove all data group copies of "defn2"
AllModels -= "defn2"
# Remove all data group copies of the unnamed model (defined
above as "wa*gaussian")
AllModels -= ""
# Remove all copies of ALL model definitions
AllModels.clear()
```

### 4.3.3 Component And Parameter Access Part 2

When PyXspec constructs a **Model** object, it immediately adds to it an attribute of type **Component** for every component in the model expression. The attribute has the same (full) name as the component in the original expression, allowing you to access it as:

```
m = Model("wa*pow")
c2 = m.powerlaw
```

However when a model contains multiple copies of the same component, this type of access becomes ambiguous. So to distinguish among copies, for any component making its 2nd or more appearance (from left to right), PyXspec will append "\_n" to the attribute name where n refers to the component's position in the expression (again from left to right). Or to put it more simply:

```
m = Model("wa*po + po")
# This gets the leftmost powerlaw component
pow1 = m.powerlaw
# This gets the rightmost, which is the 3rd component in the
expression.
pow2 = m.powerlaw_3
```

The **Model** object also stores an attribute which is a just a list of the names of its constituent **Component** attributes:

```
>>> m.componentNames
['wabs', 'powerlaw', 'powerlaw_3']
```

This may be useful for example if writing a loop to access each of a model's components. Similarly **Component** objects have a **parameterNames** attribute, listing the names of their constituent **Parameter** attributes:

```
>>> m.powerlaw.parameterNames
['PhoIndex', 'norm']
```

### 4.3.4 Flux Calculations

To perform a Standard XSPEC **flux** or **lumin** calculation, call the *AllModels* methods **calcFlux** or **calcLumin** respectively:

```
AllModels.calcFlux(".3 1.0")
AllModels.calcFlux(".1 10.0 err")
AllModels.calcLumin(".1 10. .05 err")
```

As in Standard XSPEC the results will be stored with the currently loaded spectra:

```
>>> s1 = AllData(1)
>>> s1.flux
(5.7141821510911499e-14, 0.0, 0.0, 4.0744161672429196e-05,
0.0, 0.0)
>>> s1.lumin
(30.972086553634504, 0.0, 0.0, 0.056670019567301853, 0.0, 0.0)
unless there are no spectra, in which case the results are stored with the model object:
>>> AllModels(1).flux
(5.6336924399373855e-10, 0.0, 0.0, 0.05929616315253175, 0.0,
0.0)
```

#### 4.3.5 Local Models

The Standard XSPEC **initpackage** command is not yet accessible from the PyXspec interface, so your local model library must either be built from inside a Standard XSPEC session or from the stand-alone **initpackage** tool.

[Update: AllModels.initpackage() function is now available with XSPEC patch 12.7.0a. Please see Class guide for details.]

Once it's built, you can load it with the *AllModels* **lmod** method:

```
AllModels.lmod("myLocalMods")
```

The argument string is the same package name string that you originally supplied to **initpackage**. By default this looks in the directory set by the LOCAL\_MODEL\_DIRECTORY variable in your ~/.xspec/Xspec.init start-up file. You can override this by giving **lmod** an absolute or relative path as a second string argument.

## 4.4 Fitting

### 4.4.1 Error

The **error** command is implemented through *Fit*, and the results are stored with the chosen **Parameter** object(s). The **error** attribute stores a tuple containing the low and high range values for the parameter, and the 9-letter status string to report problems incurred during the error calculation.

```
# Estimate the 90% confidence range for the 4th parameter
>>> Fit.error("2.706 4")
>>> par4 = AllModels(1)(4)
>>> par4.error
```

```
(0.11350354517707145, 0.14372981075906774, 'FFFFFFFF')
```

#### 4.4.2 Query

During a `Fit.perform()` operation, the default is to query the user whenever the fit has run the maximum number of iterations, as set by the `Fit.nIterations` attribute. You can change this behavior with the **query** attribute:

```
# When nIterations is reached, continue the fit without stopping
to query.
Fit.query = "yes"
# Stop fit at nIterations and do not query.
Fit.query = "no"
# Query the user when nIterations is reached.
Fit.query = "on"
```

#### 4.4.3 Steppar

The Standard XSPEC **steppar** command is also implemented through the global *Fit* object. You supply it with a string following the same **steppar** command syntax rules. For example:

```
# Step parameters 1 and 2 through the given range values
# over a 10x10 2-D grid.
Fit.steppar("1 20. 30. 10 2 .05 .08 10")
```

### 4.5 Fakeit

PyXspec provides access to standard XSPEC's **fakeit** command, which is for creating spectra with simulated data. It is called through the *AllData* **fakeit** method:

```
AllData.fakeit(nSpectra=1, settings=None, applyStats=True,
filePrefix="")
```

NOTE: If `AllData.fakeit` is run when spectra are currently loaded, it will follow the same rules as the standard XSPEC **fakeit** function: It will REMOVE ALL pre-existing spectra and replace each one with a simulated spectrum (even if `nSpectra` is less than the number originally loaded).

As those familiar with standard **fakeit** know, the user is normally prompted for quite a bit of additional information needed to generate the fakeit files. However the goal here is to have NO additional prompting, and that requires that all information must be



entered as arguments to the *AllData* fakeit method call. This is done by passing objects of the **FakeitSettings** class to `AllData.fakeit`, as we'll show further below.

NOTE: Unless stated otherwise, assume all spectra are OGIP **type-1** (1 spectrum per file).

For the simplest of cases, you don't need to create any **FakeitSettings** objects. Just pass in the number of fake spectra you'd like to create:

```
# Create 3 fake spectra using only default settings.  
AllData.fakeit(3)
```

The fakeit function will then create a default **FakeitSettings** object for each of the 3 spectra. By default, a **FakeitSettings** object will have empty strings for all of its attributes, and these are handled differently depending on whether the fake spectrum is replacing a currently loaded spectrum, or creating one from scratch.

#### 4.5.1 From Existing Spectra

When replacing an existing spectrum, **FakeitSettings** attributes with empty strings will simply take their value from the original spectrum. Also note that the **response** and **arf** settings for the original spectrum CANNOT be modified for the fakeit spectrum. If a name is filled in for either of these attributes, it will be ignored. If you wish to modify these, you can make the change to the original spectrum prior to calling fakeit. [The one exception is when the original spectrum has no response, in which case the response attribute MUST be filled in.] If the **fileName** attribute is empty, XSPEC will generate a default output name derived from the original file name.

#### 4.5.2 From Scratch

When creating from scratch, an empty string implies "none" for the arf and background, 1.0 for exposure and correction, and XSPEC's default dummy response for the response attribute. If the fileName attribute is empty, XSPEC will generate a default output file name based on the response name, and it will include an auto-incremented index to prevent multiple output files from overwriting each other.

#### 4.5.3 FakeitSettings Objects

To create a fake spectrum with anything other than default settings, you must supply a **FakeitSettings** object for that spectrum. The **FakeitSettings** attributes are: response, arf, background, exposure, correction, backExposure, and fileName. All are string types, though exposure, backExposure, and correction can also be entered as floats. Attributes can be set upon object construction, or anytime afterwards:

```
fs1 = FakeitSettings("response1.rsp", exposure = 1500.0)
```

```
fs1.background = "back1.pha"
```

A new FakeitSettings object can also be made by copying an existing one:

```
fs2 = FakeitSettings(fs1)
```

And now pass the objects to the fakeit method, either in a list, dictionary, or as a single object:

```
# Apply settings to fakeit spectra 1 and 2:
```

```
AllData.fakeit(2, [fs1, fs2])
```

```
# Apply setting to fakeit spectrum 1, use defaults for spectrum 2:
```

```
AllData.fakeit(2, fs1)
```

```
# Apply settings to fakeit spectra 2 and 4, use defaults for 1 and 3:
```

```
settingsDict = {2:fs1, 4:fs2}
```

```
AllData.fakeit(4, settingsDict)
```

```
# Create 4 fakeit spectra from the same settings object:
```

```
settingsList = 4*[fs1]
```

```
AllData.fakeit(4, settingsList)
```

The remaining 2 arguments to the AllData.fakeit function are for choosing whether to apply statistical fluctuations (default = True), and whether to add an optional prefix string to the names of all output files.

#### 4.5.4 OGIP Type-2 Files

With **OGIP type-2** files, multiple spectra may be placed in a single file. The important thing to recognize when generating type-2 fakeit files is that the **exposure**, **correction**, **backExposure**, and **fileName** attributes apply to the output files and not the individual spectra. Therefore these settings will be ignored for all but the first spectrum in a file. For example:

```
# Start with 4 spectra loaded, in 2 type-2 files:
```

```
AllData("myDataFile1.pha{1-2} myDataFile2.pha{7-8}")
```

```
# Create settings for the 4 fake spectra that will be generated from these:
```

```
fs1 = FakeitSettings(background="back1.pha", exposure=250.)
```

```
# The exposure setting in fs2 will be ignored!!!
```

```
fs2 = FakeitSettings(background="back2.pha", exposure 100.)
```

```

fs3 = FakeitSettings(fileName="myFakeitFile_2.pha")
fs4 = FakeitSettings(fs3)
# The following change will be ignored!!!
fs4.fileName = "myFakeitFile_3.pha"
# Now generate the fakeit files: AllData.fakeit(4, [fs1,fs2,fs3,fs4])

```

The above will generate 4 fakeit spectra, placed in 2 type-2 files. The exposure setting for spectrum 2 and the fileName setting for spectrum 4 will be ignored. Those values are only set by spectra 1 and 3.

For more fakeit details and examples, please check:

```

>>>help(FakeitSettings)
>>>help(DataManager.fakeit)

```

## 4.6 Monte Carlo Markov Chains (MCMC)

All MCMC operations are handled either by objects of class **Chain**, or the global *AllChains* container object. To create a new chain based on the current fit parameters, simply create a **Chain** object by passing it an output file name:

```
c1 = Chain("chain1.fits")
```

The above call creates the file "chain1.fits", performs an MCMC run using the default *burn*, *fileType*, *length*, *proposal*, *rand*, and *temperature* values, and automatically places the new object in the *AllChains* container. These default settings are stored as attributes of *AllChains*:

```

# Ensure that new chains will burn the first 100 iterations,
will
# have length 1000, and will use the proposal "gaussian fit"
AllChains.defBurn = 100
AllChains.defLength = 1000
AllChains.defProposal = "gaussian fit"
c2 = Chain("chain2.fits")

```

You can also override the *AllChains* default settings by passing additional arguments to **Chain** upon construction:

```

# Length will be 2000 for this chain, use defaults for all
other settings.
c3 = Chain("chain3.fits", runLength = 2000)

```

The new chain objects will then store their own settings as attributes:

```
>>>c2.burn
100
>>>c2.runLength
1000
>>>c3.runLength
2000
```

All of a chain object's attributes will be displayed when calling its `show()` method.

To append a new run to an existing chain object, call the object's `run()` method. The appending run will use the object's current attribute settings, and not the *AllChains* default settings:

```
# This will append a run of length 3000 to the c3 chain object,
and with a
# Metropolis-Hastings temperature of 50.0:
c3.runLength = 3000
c3.temperature = 50.0
c3.run()
>>> c3.totalLength
5000
```

To **overwrite** rather than append to an existing chain object, call `run` with its `append` argument set to `False`:

```
# This erases the results of any previous runs for object c3.
c3.run(False)
>>> c3.totalLength
3000
```

New chains are loaded into *AllChains* by default, but you can unload or reload them using the *AllChains* arithmetic operators:

```
# Chain c2 may be unloaded by passing its chain index number
AllChains -= 2
# OR by passing the object itself
AllChains -= c2
# 2 ways to remove ALL chains
AllChains -= '*'
AllChains.clear()
```

```
# Reload an existing chain object
AllChains += c2

# Load a chain from an existing chain file
AllChains += "earlierChain.fits"

# Create a new chain, to be stored in file "chain4.fits"
AllChains += "chain4.fits"
```

As with Standard XSPEC, unloading a chain will leave the chain's file intact. It merely removes the chain from XSPEC's calculations. To display information about the currently loaded chains, call `AllChains.show()`.

You may also get a chain object from the container at any time by passing it an index number:

```
# Retrieve a chain object for the 4th chain in the container
c4 = AllChains(4)
```

## 4.7 Plotting

All of the plotting options available in Standard XSPEC's **setplot** command are now implemented as attributes of the *Plot* object. Some of these are mentioned in the Quick Version of the tutorial, and please see the *PlotManager* class reference for the complete guide.

One setting of particular interest is the **commands** attribute. This is a tuple of user-entered **PLT** command strings which are added to XSPEC's auto-generated commands when performing a plot, and is modified through *Plot*'s **addCommand** and **delCommand** methods. For example, to enter a PLT command to place an additional label at the specified coordinates on the plot:

```
Plot.addCommand("label 1 pos 10 .05 \"Another Label\"")
```

To view the currently loaded commands:

```
print Plot.commands
```

and to remove the 3rd command from the tuple:

```
Plot.delCommand(3)
```

## 4.8 XSPEC Settings

Most of the internal switches set through Standard XSPEC's **xset** command are now set through attributes of the global *Xset* object. Examples:

```
Xset.abund = "angr"
```

```
Xset.cosmo = "50 .5 0."
```

```
Xset.xsect = "bcmc"
```

*Xset* also provides the methods **addModelString** and **delModelString** to set the <string name>,<string value> pairs which are used by certain models. The <string name> argument is case-insensitive.

```
Xset.addModelString("APECROOT", "1.3.1")
```

```
Xset.addModelString("APECTHERMAL", "yes")
```

```
Xset.delModelString("neivers")
```

The entire collection of <name>,<value> pairs may be set or retrieved with the *Xset.modelStrings* attribute:

```
# Replace all previous entries with a new dictionary
```

```
Xset.modelStrings = {"neivers":"1.1", "apecroot":"1.3.1"}
```

```
# Clear out all entries:
```

```
Xset.modelStrings = {}
```

*Xset.show()* will display all of the current settings including the current <string name>,<string value> pairs.

## 4.9 Logging And XSPEC Output

The *Xset* object provides attributes and methods for controlling output chatter level and for creating log files:

```
# Get/Set the console chatter level
```

```
ch = Xset.chatter
```

```
Xset.chatter = 10
```

```
# Get/Set the log chatter level
```

```
lch = Xset.logChatter
```

```
Xset.logChatter = 20
```

```
# Create and open a log file for XSPEC output
```

```
# This returns a Python file object
```

```
logFile = Xset.openLog("newLogFile.txt")
```

```
# Get the Python file object for the currently opened log
```

```
logFile = Xset.log
```

```
# Close XSPEC's currently opened log file.
```

```
Xset.closeLog()
```

## 4.10 Exceptions And Error Handling

PyXspec utilizes the standard Python **try/except/raise** mechanism for handling and reporting errors. In this early version, only exception objects of the class **Exception** are ever raised. In the future other (more specific) error classes may be used, but they should always be derived from **Exception**. So you can catch all PyXspec exceptions with code such as:

```
try:
    # Only 4 spectra are currently loaded
    s = xspec.AllData(5)
except Exception, msg:
    print msg
```

which will print the error message:

```
Error: Spectrum index number is out of range: 5
```

PyXspec raises errors in a variety of situations, such as for invalid input argument syntax, or for input which is invalid within the context of the call (as in the example above). It can also raise exceptions if you try to rebind a class attribute when such modification is not permitted.

## 4.11 Adding Attributes To PyXspec Objects

A particularly novel feature of Python (in comparison with say C++) is that it allows you to create new attributes "on the fly". The attributes don't have to have been part of the original class definition:

```
class C:
    pass

x = C()
x.pi = 3.1416
```

The downside of course is that spelling or case sensitive errors become much harder to detect. For example, with PyXspec's *Plot* object:

```
Plot.yLog = True # Correct
Plot.ylog = True # Wrong!
```

In the second case, standard Python will simply add a new attribute named "ylog" to *Plot*, and this will have no effect on the actual plot since PyXspec is only looking at "yLog".

So operating under the assumption that this downside outweighs the benefits, we've decided to **disable** the ability to add new attributes to PyXspec class objects. A misspelling or case error will instead raise an **Exception** object. And since some users may genuinely wish to add their own attributes to PyXspec classes, this default behavior may be overridden by toggling the **Xset.allowNewAttributes** flag:

```
s = Spectrum("dataFile.pha")
s.myNewIndex = 10 # Error: Will raise an exception
Xset.allowNewAttributes = True
s.myNewIndex = 10 # OK
.
. # Can add new attributes to any PyXspec object,
. # but attribute spelling errors will go undetected.
.
Xset.allowNewAttributes = False
```

## 4.12 Using With Other Packages

One of the primary benefits of PyXspec is that it makes it much easier to use XSPEC data and results in 3rd party packages. For example you can bypass XSPEC's built-in plotting functions in favor of a Python plotting library such as Matplotlib:

```
#!/usr/bin/python
from xspec import *
import matplotlib.pyplot as plt
# PyXspec operations:
s = Spectrum("file1.pha")
m = Model("wa*po")
Fit.perform()
# Plot using Matplotlib:
plt.plot(s.noticed, s.values, 'ro', s.noticed, m.folded(1))
plt.xlabel('channels')
plt.ylabel('counts/cm^2/sec/chan')
```



```
plt.savefig('myplot')
```

The above code produces a Matplotlib plot of the spectral data and folded model vs. channels (similar to what you get with Standard XSPEC's "plot data" command). It makes use of the **Spectrum** object's **noticed** attribute to pass a list of the channel numbers, and the **values** attribute (a tuple) to pass the spectral data values in counts/cm<sup>2</sup>/s. The folded model values are obtained as a list by calling the **Model** object's **folded** method with a spectrum number argument.

## 5 What's Missing

Python equivalents for these standard XSPEC commands are not yet implemented in the beta release:

- bayes\*
- gain
- goodness\*
- hardcopy
- identify
- improve\*
- initpackage\*
- margin
- mdefine
- Tcl script commands: addline, lrt, modid, multifake, rescalecov, simftest, write-fits

(\*)Now available with patch 12.7.0a

The following commands perform functions which are not applicable to the currently intended design and usage of PyXspec, and therefore are not likely to be implemented in the near future:

- addcomp
- autosave
- delcomp
- editmod
- save
- script

## 6 Class Index

### 6.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">Background</a>	31
<a href="#">Chain</a>	34
<a href="#">ChainManager</a>	38
<a href="#">Component</a>	42
<a href="#">DataManager</a>	43
<a href="#">FakeitSettings</a>	49
<a href="#">FitManager</a>	53
<a href="#">Model</a>	61
<a href="#">ModelManager</a>	68
<a href="#">Parameter</a>	74
<a href="#">PlotManager</a>	79
<a href="#">Response</a>	88
<a href="#">Spectrum</a>	90
<a href="#">XspecSettings</a>	101

## 7 Class Documentation

### 7.1 Background Class Reference

#### Public Member Functions

- [def \\_\\_init\\_\\_](#)

#### Public Attributes

- [areaScale](#)

The *Background* area scaling factor (GET only).

- **exposure**

The exposure time keyword value [float] (GET only).

- **fileName**

The spectrum's file name [string] (GET only).

- **isPoisson**

Boolean flag, True if spectrum has Poisson errors (GET only).

- **values**

Tuple of floats containing the background rates array in counts/cm<sup>2</sup>-sec (GET only).

- **variance**

Tuple of floats containing the variance of each channel (GET only).

### 7.1.1 Detailed Description

Background spectral data class.

Public instance attributes (implemented as properties):

```

areaScale    -- The Background area scaling factor (GET only).
               Either a single float (if file stores it as a keyword),
               or a Tuple of floats (if file stores column).

exposure     -- The exposure time keyword value [float] (GET only).

fileName     -- The spectrum's file name [string] (GET only).

isPoisson    -- Boolean flag, True if spectrum has Poisson errors
               (GET only).

values       -- Tuple of floats containing the background rates array in
               counts/cm^2-sec (GET only).

variance     -- Tuple of floats containing the variance of each
               channel (GET only).
```

### 7.1.2 Constructor & Destructor Documentation

#### 7.1.2.1 `def __init__( self, backTuple, parent )`

Construct a Background object.

Intended for creation by a Spectrum object only.  
The parent arg should be the Spectrum object's self pointer.

### **7.1.3 Member Data Documentation**

#### **7.1.3.1 areaScale**

The [Background](#) area scaling factor (GET only).

Either a single float (if file stores it as a keyword),  
or a Tuple of floats (if file stores column).

#### **7.1.3.2 exposure**

The exposure time keyword value [float] (GET only).

#### **7.1.3.3 fileName**

The spectrum's file name [string] (GET only).

#### **7.1.3.4 isPoisson**

Boolean flag, True if spectrum has Poisson errors (GET only).

#### **7.1.3.5 values**

Tuple of floats containing the background rates array in counts/cm<sup>2</sup>-sec (GET only).

#### **7.1.3.6 variance**

Tuple of floats containing the variance of each channel (GET only).

The documentation for this class was generated from the following file:

- spectrum.py

## 7.2 Chain Class Reference

### Public Member Functions

- def `__init__`
- def `run`
- def `show`

### Public Attributes

- `burn`  
*The number of steps that will be thrown away prior to storing the chain [int].*
- `runLength`  
*The length of chain to be added during the next run [int].*
- `proposal`  
*The proposal distribution and source of covariance information to be used for the next run [string].*
- `rand`  
*Determines whether chain start point will be randomized (True) or taken from the current parameters (False).*
- `temperature`  
*The temperature parameter used in the Metropolis-Hastings algorithm for the proposal acceptance or rejection [float].*
- `fileName`  
*Chain output file name.*
- `fileType`  
*Output format of the chain file [string].*
- `totalLength`  
*The cumulative length of the chain [int].*

### 7.2.1 Detailed Description

Monte Carlo Markov Chain class.

Public instance attributes:

GET-only attributes:

```

fileName    -- Chain output file name.
fileType    -- Output format of the chain file [string].
               Will be either "fits" (the default), or "ascii".
totalLength -- The cumulative length of the chain [int].
               This will increase every time a run is performed.

```

The following attribute settings will apply to the NEXT run for this chain. The burn and rand settings are irrelevant if run is performing an appending operation.

```

runLength   -- The length of chain to be added during the next run [int].
proposal     -- The proposal distribution and source of covariance
               information to be used for the next run [string].
               Examples: "gaussian fit", "cauchy fit",
               "gaussian chain", etc.
               See the "chain" command in the standard XSPEC manual
               for more information.
temperature -- The temperature parameter used in the Metropolis-Hastings
               algorithm for the proposal acceptance or rejection
               [float].
burn         -- The number of steps that will be thrown away prior to
               storing the chain [int].
rand         -- Determines whether chain start point will be randomized
               (True) or taken from the current parameters (False).

```

### 7.2.2 Constructor & Destructor Documentation

**7.2.2.1** `def __init__( self, fileName, fileType = None, burn = None, runLength = None, proposal = None, rand = None, temperature = None )`

Construct a chain object, perform a run, and load into AllChains container.

The only required argument is fileName. All other arguments will take their default values from the current settings in the AllChains container.

### 7.2.3 Member Function Documentation

#### 7.2.3.1 `def run ( self, append = True )`

Perform a new chain run, either appending to or overwriting an existing chain.

`append` -- If this is set to `True` the new run will be appended. If `False`, the new run will overwrite. Note that the `burn` and `rand` settings do not apply when appending.

#### 7.2.3.2 `def show ( self )`

Display current settings of Chain object's attributes.

### 7.2.4 Member Data Documentation

#### 7.2.4.1 `burn`

The number of steps that will be thrown away prior to storing the chain [int].

#### 7.2.4.2 `fileName`

[Chain](#) output file name.

#### 7.2.4.3 `fileType`

Output format of the chain file [string].

Will be either `"fits"` (the default), or `"ascii"`.

#### 7.2.4.4 proposal

The proposal distribution and source of covariance information to be used for the next run [string].

```
Examples: "gaussian fit", "cauchy fit",  
          "gaussian chain", etc.  
See the "chain" command in the standard XSPEC manual  
for more information.
```

#### 7.2.4.5 rand

Determines whether chain start point will be randomized (True) or taken from the current parameters (False).

#### 7.2.4.6 runLength

The length of chain to be added during the next run [int].

#### 7.2.4.7 temperature

The temperature parameter used in the Metropolis-Hastings algorithm for the proposal acceptance or rejection [float].

#### 7.2.4.8 totalLength

The cumulative length of the chain [int].

```
This will increase every time a run is performed.
```

The documentation for this class was generated from the following file:

- chain.py



## 7.3 ChainManager Class Reference

### Public Member Functions

- `def __init__`
- `def __call__`
- `def __iadd__`
- `def __isub__`
- `def clear`
- `def show`
- `def stat`

### Public Attributes

- `defBurn`  
*Default burn length for new [Chain](#) objects (orig = 0).*
- `defFileType`  
*Default output file format (orig = "fits").*
- `defLength`  
*Default chain length (orig = 100).*
- `defProposal`  
*Default chain proposal (orig = "gaussian fit").*
- `defRand`  
*Default randomization setting (orig = False).*
- `defTemperature`  
*Default chain temperature (orig = 1.0).*

### 7.3.1 Detailed Description

Monte Carlo Markov Chain container.

This is a singleton - only 1 instance allowed

Public instance attributes:

These are the values which will be used when creating new Chain objects, unless they are explicitly overridden as arguments to the Chain class constructor. For more detail, see the descriptions for the corresponding attributes in the Chain class doc.

```

defBurn          -- Default burn length for new Chain objects (orig = 0).
defFileType      -- Default output file format (orig = "fits").
defLength        -- Default chain length (orig = 100).
defProposal      -- Default chain proposal (orig = "gaussian fit").
defRand          -- Default randomization setting (orig = False).
defTemperature   -- Default chain temperature (orig = 1.0).

```

### 7.3.2 Constructor & Destructor Documentation

#### 7.3.2.1 `def __init__( self )`

### 7.3.3 Member Function Documentation

#### 7.3.3.1 `def __call__( self, index )`

Get a Chain object from the AllChains container.

```

index -- The index of a currently loaded chain file. The list
of currently loaded chains can be seen with the
AllChains.show() method. The valid range is:
1 <= index <= nLoadedChains.

```

Note that the returned Chain object's modifiable attributes will be initialized with the current AllChains def<attribute> settings.

Example:

```

# Load 2 chains from pre-existing files:
AllChains += "chain1.fits"
AllChains += "chain2.fits"
# and get a Chain object for the 2nd chain:
c2 = AllChains(2)

```

#### 7.3.3.2 `def __iadd__( self, chain )`

Load a pre-existing chain into the AllChains container.

Argument may be a currently existing chain object which had been unloaded earlier:

```

AllChains += myChain1
the filename of an existing chain file:

```

```
AllChains += "chainFile.fits"
or the filename of a new chain:
    AllChains += "newChainFile.fits" # This will also perform a chain
                                     # run using the default settings.
```

### 7.3.3.3 def \_\_isub\_\_( self, chain )

Unload one or more chain objects from container.

Argument may either be a chain object:

```
AllChains -= myChain1
```

a filename:

```
AllChains -= "chainFile.fits"
```

the chain's current index [int] in the AllChains container:

```
AllChains -= 2
```

or a '\*' to unload ALL chains (equivalent to AllChains.clear()):

```
AllChains -= '*'
```

### 7.3.3.4 def clear ( self )

Unload all chains from container

### 7.3.3.5 def show ( self )

Display information for current attributes and loaded chains.

### 7.3.3.6 def stat ( self, parIdx )

Display statistical information on a particular chain parameter.

```
parIdx -- The parameter index number, including optional model
name: [<modelName>:]<idx>. May be entered as a string
or int (if no model name).
```

### 7.3.4 Member Data Documentation

#### 7.3.4.1 defBurn

Default burn length for new [Chain](#) objects (orig = 0).

#### 7.3.4.2 defFileType

Default output file format (orig = "fits").

#### 7.3.4.3 defLength

Default chain length (orig = 100).

#### 7.3.4.4 defProposal

Default chain proposal (orig = "gaussian fit").

#### 7.3.4.5 defRand

Default randomization setting (orig = False).

#### 7.3.4.6 defTemperature

Default chain temperature (orig = 1.0).

The documentation for this class was generated from the following file:

- chain.py

## 7.4 Component Class Reference

### Public Member Functions

- `def __init__`
- `def __setattr__`

### Public Attributes

- `name`  
*The full name of the `Component` (get only).*
- `parameterNames`  
*List of Component's parameter names (get only).*

#### 7.4.1 Detailed Description

Model component class.

Public instance attributes:

```

name          -- The full name of the Component (get only).

<parameters>  -- Component contains an attribute of type Parameter for
                  every parameter in the component. The attribute
                  name is the same as the parameter name in xspec.

parameterNames -- List of Component's parameter names (get only).
```

#### 7.4.2 Constructor & Destructor Documentation

##### 7.4.2.1 `def __init__( self, compName, parNames )`

Component constructor.

Intended for creation by Model objects only.

```

compName  -- The full xspec component name. This will also
            be the name of the attribute in the model object
parNames  -- List containing component's parameter names.
```

### 7.4.3 Member Function Documentation

#### 7.4.3.1 `def __setattr__ ( self, attrName, value )`

### 7.4.4 Member Data Documentation

#### 7.4.4.1 `name`

The full name of the [Component](#) (get only).

#### 7.4.4.2 `parameterNames`

List of Component's parameter names (get only).

The documentation for this class was generated from the following file:

- `model.py`

## 7.5 DataManager Class Reference

### Public Member Functions

- `def __init__`
- `def __call__`
- `def __isub__`
- `def __iadd__`
- `def clear`
- `def diagrsp`
- `def dummyrsp`
- `def fakeit`
- `def ignore`
- `def notice`
- `def removeDummyrsp`
- `def show`

### Public Attributes

- [nGroups](#)  
*The number of data groups [int].*
- [nSpectra](#)  
*The number of loaded spectra [int].*

#### 7.5.1 Detailed Description

Spectral data container.

This is a singleton - only 1 instance allowed

Public instance attributes, GET only unless stated otherwise.

```
nGroups -- The number of data groups [int].
nSpectra -- The number of loaded spectra [int].
```

#### 7.5.2 Constructor & Destructor Documentation

##### 7.5.2.1 `def __init__( self )`

#### 7.5.3 Member Function Documentation

##### 7.5.3.1 `def __call__( self, expr )`

DataManager get or set spectra.

Get:

```
expr -- An integer referring to the spectrum index number. Returns
the spectrum, or raises an Exception if the integer is out
of range.
```

Set:

```
expr -- A string following the same syntax rules as Xspec's
traditional "data" command handler.
```

##### 7.5.3.2 `def __iadd__( self, spectra )`

Add 1 spectrum to the data container.

spectra - the data filename string.

#### 7.5.3.3 `def __isub__( self, spectra )`

Remove 1 or all spectra from the data container.

spectra - either a single spectrum index number (int), a single Spectrum object, or the string "\*" to remove all.

#### 7.5.3.4 `def clear ( self )`

Remove all spectra from the data container.

#### 7.5.3.5 `def diagsp ( self )`

Diagonalize the current response matrix for ideal response.

All currently loaded responses will be replaced with diagonal response matrices. The energy range and channel binning information are retained from the original response, as is the effective area. The channel values are mapped directly into the corresponding energy ranges to simulate a detector with perfect spectral resolution.

To remove diagonal responses and restore the originals, call the `AllData.removeDummyrsp()` method.

#### 7.5.3.6 `def dummyrsp ( self, lowE = None, highE = None, nBins = None, scaleType = None, chanOffset = None, chanWidth = None )`

Create a dummy response and apply it to all spectra.

Input arguments, all are optional:



```

lowE - Input response energy lower bound, in keV. [float]
highE - Input response energy higher bound, in keV. [float]
nBins - Number of bins into which the energy range is divided
        [int].
scaleType - "log" or "lin" [string]
chanOffset - Starting value of dummy channel energies. [float]
chanWidth - Energy width of the channel bins. [float]
             If this is set to 0, the dummy response
             can only be used for evaluating model arrays,
             and not for fitting to spectra.

```

Examples:

```

# All values are optional, use keywords to enter values
# non-consecutively. Unspecified values revert to the
# current defaults.
AllData.dummyrsp(.3, 30., 100, chanWidth=.5)
AllData.dummyrsp(highE = 50.)
AllData.dummyrsp(.1,10.,100,"lin",.0, 1.0)

Initial defaults: lowE = .1, highE = 50., nBins = 50, scaleType = "log"
                  chanOffset = .0, chanWidth = .0
The defaults for lowE, highE, nBins, scaleType, and chanOffset will be
modified for each explicit new entry. chanWidth always defaults to 0.

To remove dummy responses and restore actual responses (if any), call
the removeDummyrsp() method.

To apply a dummy response to just a single spectrum, use the
Spectrum.dummyrsp method.

```

### 7.5.3.7 def fakeit ( self, nSpectra = 1, settings = None, applyStats = True, filePrefix = "" )

Produce spectra with simulated data using XSPEC's fakeit command.

Note that if this method is run when spectra are currently loaded, it will follow the same rule as the standard XSPEC fakeit function: It will REMOVE ALL pre-existing spectra and replace each one with a simulated spectrum (even if nSpectra is less than the number originally loaded).

All arguments are optional:

```

nSpectra  -- The number of fake spectra to produce. [int]

             If there are nOrig pre-existing spectra loaded at the
             time this function is called and nSpectra < nOrig,
             nSpectra will be RESET to nOrig (see note above).

             If nSpectra == nOrig, then each of the fake spectra

```

will use the settings from the respective original spectra for their defaults (see the FakeitSettings class description).

If nSpectra > nOrig, then settings for the fake spectra numbered above nOrig will not be based on pre-existing spectra (if any).

settings -- A collection of 0 to nSpectra FakeitSettings objects, which may be entered as a list, a dictionary, a single FakeitSettings object, or None.

If settings is a dictionary, the key,value pairs should be the spectrum index number (1 is lowest) and the FakeitSettings object.

This function will match up FakeitSettings objects 1-to-1 with the nSpectra fake spectra to be created.

If user provides FEWER than nSpectra FakeitSettings objects, fakeit will generate the necessary additional objects with their default settings.

If MORE than nSpectra FakeitSettings objects are provided, the extra objects will be ignored.

applyStats -- If set to True, statistical fluctuations will be included in the generation of fake spectra. [bool]

filePrefix -- Optional string to attach as a prefix to default fakeit output file names. Note that this only applies when using the default file names. If a file name is explicitly entered in the FakeitSettings.fileName attribute, it will not make use of this.

Examples:

```
# Assume no data is loaded, but a model is defined:
```

```
AllData.fakeit()
# Creates 1 fake spectrum using the default FakeitSettings object,
# which has all input strings empty. So it will use XSPEC's internal
# dummy response and its output file name will be dummy_rsp_1.fak.
```

```
# Now assume AllData contains 2 spectra PRIOR to running EACH of the
# following commands, then:
```

```
AllData.fakeit()
# Creates 2 fake spectra with all settings (response, arf,
# background, exposure, corrscale, backExposure, filenames) based
# on the original spectra. The original 2 spectra are removed from
# AllData.
```

```
AllData.fakeit(3)
# Creates the first 2 spectra as above. The 3rd fake spectrum is
# based on the default FakeitSettings object and its output filename
# will be dummy_rsp_3.fak
```

```

fs = FakeitSettings(background="back1.pha", exposure=2000.0)
sl = 3*[fs]
AllData.fakeit(3, sl)
# Same as above, but all 3 fake spectra will have a background file
# based on back1.pha, and exposure time = 2000.0 sec.

AllData.fakeit(3, sl, False, "my_fake_")
# Same as above, but no statistical fluctuations will be applied to
# fake spectra, and all output files will have the "my_fake_"
# prefix attached.

fs1 = FakeitSettings("resp1.rmfi", "arf1.pha", exposure=1500.)
fs2 = FakeitSettings(fs1)
fs2.response = "resp2.rmfi"
sd = {3:fs1, 5:fs2}
AllData.fakeit(5, sd)
# Creates 5 fake spectra. The first 2 use the settings from the
# originally loaded data. Spectra 3 and 5 use the settings from
# the fs1 and fs2 FakeitSettings objects, which differ only in their
# response names. Spectrum 4 uses the default FakeitSettings object.

```

### 7.5.3.8 def ignore ( self, ignoreRange )

Apply an ignore channels range to multiple loaded spectra.

```

ignoreRange -- String specifying the spectra ranges and/or
channel ranges to ignore, or "bad".
This follows the same syntax as used in the standard
Xspec "ignore" command, except that the spectrum range
always defaults to ALL spectra.

```

If the channel ranges are floats rather than ints,  
they will be treated as energies or wavelengths  
(depending on the Plot settings).

### 7.5.3.9 def notice ( self, noticeRange )

Apply a notice channels range to multiple loaded spectra.

```

noticeRange -- String specifying the spectra ranges and/or channel
ranges to notice. This follows the same syntax as
used in the standard Xspec "notice" command, except
that the spectrum range always defaults to ALL spectra.

```

If the numbers are floats rather than ints, they will

be treated as energies or wavelengths (depending on the Plot settings). If the string is "all", it will notice all channels in all spectra.

#### 7.5.3.10 def removeDummyrsp ( *self* )

Remove all dummy responses, restore original responses (if any).

#### 7.5.3.11 def show ( *self* )

Display information for all loaded spectra.

### 7.5.4 Member Data Documentation

#### 7.5.4.1 nGroups

The number of data groups [int].

#### 7.5.4.2 nSpectra

The number of loaded spectra [int].

The documentation for this class was generated from the following file:

- data.py

## 7.6 FakeitSettings Class Reference

### Public Member Functions

- def [\\_\\_init\\_\\_](#)

### Public Attributes

- [response](#)  
*Name of detector response file to use for creating the fake spectrum.*
- [arf](#)  
*Name of optional arf to use with the response.*
- [background](#)  
*Name of optional background file to use when creating the fake spectrum.*
- [exposure](#)  
*The fake spectrum exposure time.*
- [correction](#)  
*Optional correction norm factor.*
- [backExposure](#)  
*Optional background exposure time modifier.*
- [fileName](#)  
*Optional fake spectrum output file name.*

#### 7.6.1 Detailed Description

Fakeit command settings class.

The AllData.fakeit function will apply 1 FakeitSettings object to every fake spectrum that is to be created. If the user does not explicitly supply their own FakeitSettings objects, AllData.fakeit will create its own as necessary, with default settings.

Public instance attributes [all are string types unless noted]:

```
response    -- Name of detector response file to use for creating the
               fake spectrum.
```

When a fake spectrum is based on a pre-existing spectrum which already has a response, this should be left empty. If a name is given it will be IGNORED. However if the pre-existing spectrum has no response, then this MUST be filled.

If the fake spectrum is not based on an existing spectrum, this may be filled or left empty. If it is empty, XSPEC will just use its built-in dummy response.

```

arf          -- Name of optional arf to use with the response.  This is
               ignored if no response is given.

background -- Name of optional background file to use when creating the
               fake spectrum.

               If based on an original spectrum, leave this empty to use
               the original spectrum's background settings.

exposure     -- The fake spectrum exposure time.

correction   -- Optional correction norm factor.

backExposure -- Optional background exposure time modifier.

               For exposure and correction, if left empty fakeit will use
               the values from the original spectrum, or 1.0 if not
               based on an original spectrum.  Each of these may be
               entered as a string or float.

fileName     -- Optional fake spectrum output file name.

               If left empty, fakeit will create a default file name
               based on the original spectrum, or the response name
               if no original spectrum.  In the latter case, the
               default names will also have an incremented suffix to
               prevent file overwriting.

```

When writing to a multiple-spectrum output file (OGIP type-2), exposure, correction, backExposure, and fileName are applied to the entire file rather than a single spectrum. Therefore entries for these attributes will be IGNORED for all but the first fake spectrum in a type-2 output file.

## 7.6.2 Constructor & Destructor Documentation

**7.6.2.1** `def __init__( self, response = "", arf = "", background = "", exposure = "", correction = "", backExposure = "", fileName = "" )`

Create a FakeitSettings object.

All arguments are optional, and all may be entered as strings. The exposure and correction arguments may also be entered as floats.

This can also create a new copy of a pre-existing FakeitSettings object, in which case the pre-existing object should be the only argument entered.

Examples:

```

fsl = FakeitSettings("respl.pha", exposure=1500.0)
# Reuse fsl's settings, but with a new fileName attribute:

```

```
fs2 = FakeitSettings(fs1)
fs2.fileName = "fakeit2.pha"
# Now generate 2 fake spectra
AllData.fakeit(2, [fs1, fs2])
```

### 7.6.3 Member Data Documentation

#### 7.6.3.1 arf

Name of optional arf to use with the response.

This is

```
ignored if no response is given.
```

#### 7.6.3.2 backExposure

Optional background exposure time modifier.

```
For exposure and correction, if left empty fakeit will use
the values from the original spectrum, or 1.0 if not
based on an original spectrum. Each of these may be
entered as a string or float.
```

#### 7.6.3.3 background

Name of optional background file to use when creating the fake spectrum.

```
If based on an original spectrum, leave this empty to use
the original spectrum's background settings.
```

#### 7.6.3.4 correction

Optional correction norm factor.

### 7.6.3.5 exposure

The fake spectrum exposure time.

### 7.6.3.6 fileName

Optional fake spectrum output file name.

If left empty, fakeit will create a default file name based on the original spectrum, or the response name if no original spectrum. In the latter case, the default names will also have an incremented suffix to prevent file overwriting.

### 7.6.3.7 response

Name of detector response file to use for creating the fake spectrum.

When a fake spectrum is based on a pre-existing spectrum which already has a response, this should be left empty. If a name is given it will be IGNORED. However if the pre-existing spectrum has no response, then this MUST be filled.

If the fake spectrum is not based on an existing spectrum, this may be filled or left empty. If it is empty, XSPEC will just use its built-in dummy response.

The documentation for this class was generated from the following file:

- data.py

## 7.7 FitManager Class Reference

### Public Member Functions

- def [\\_\\_init\\_\\_](#)
- def [error](#)
- def [ftest](#)



- def [goodness](#)
- def [improve](#)
- def [perform](#)
- def [renorm](#)
- def [show](#)
- def [steppar](#)

#### Public Attributes

- [bayes](#)  
*Turn Bayesian inference on or off [string].*
- [criticalDelta](#)  
*Critical delta for fit statistic convergence [float].*
- [delta](#)  
*Set fit delta values to be proportional to the parameter value [float].*
- [dof](#)  
*The degrees of freedom for the fit [int] (GET only).*
- [method](#)  
*The fitting algorithm to use [string].*
- [nIterations](#)  
*The maximum number of fit iterations prior to query [int].*
- [query](#)  
*The fit query setting [string].*
- [statistic](#)  
*Fit statistic value from the most recent fit [float] (GET only).*
- [statMethod](#)  
*The type of fit statistic in use [string].*
- [weight](#)  
*Change the weighting function used in the calculation of chi-sq [string].*

### 7.7.1 Detailed Description

Xspec fitting class.

This is a singleton - only 1 instance allowed

Public instance attributes (implemented as properties):

```

bayes          -- Turn Bayesian inference on or off [string].

                *Available with XSPEC patch 12.7.0a

                Valid settings are "on", "off" (default), or "cons".
                "cons" turns Bayesian inference on AND gives ALL
                parameters a constant prior. Priors can be set for
                parameters individually through the Parameter object's
                'prior' attribute.

criticalDelta  -- Critical delta for fit statistic convergence [float].
                The absolute change in the fit statistic between
                iterations, less than which the fit is deemed to
                have converged.

delta          -- Set fit delta values to be proportional to the
                parameter value [float].

                Get: Returns the current proportional setting, or 0.0 if
                currently using the fixed fit delta values.

                Set: Enter the constant factor which will multiply the
                parameter value to produce a fit delta. A constant
                factor of 0.0 or negative will turn off the use of
                proportional fit deltas.

dof           -- The degrees of freedom for the fit [int] (GET only).

method        -- The fitting algorithm to use [string].

                Choices are: "leven", "migrad", "minimize", "monte",
                "simplex". The default is "leven".

                When setting the method, additional arguments for
                <nFitIterations> and <fit critical delta> may also be
                entered. Valid formats for entering multiple
                arguments are:

                # Single string
                Fit.method = "migrad 100 .05"
                # List of strings
                Fit.method = ["migrad", "100", ".05"]
                # List of strings and numbers
                Fit.method = ["migrad", 100, .05]

nIterations   -- The maximum number of fit iterations prior to query [int].

query        -- The fit query setting [string].
                "yes": Fit will continue through query.

```

```

        "no" : Fit will end at query.
        "on" : User will be prompted for "y/n" response.

    statistic      -- Fit statistic value from the most recent fit [float]
                    (GET only).

    statMethod     -- The type of fit statistic in use [string].
                    Valid names: "chi" | "cstat" | "lstat"

    weight         -- Change the weighting function used in the calculation of
                    chi-sq [string].

                    Available functions: "standard", "gehrrels",
                    "churazov", "model"

```

### 7.7.2 Constructor & Destructor Documentation

#### 7.7.2.1 `def __init__( self )`

### 7.7.3 Member Function Documentation

#### 7.7.3.1 `def error( self, argString )`

Determine confidence intervals of a fit.

Input: `argString` is a string with identical syntax to the standard interactive XSPEC error command.

```

"[[stopat <ntrial> <toler>] [maximum <redchi>]
  [<delta fit statistic>] [<model param range>...]]"
```

where:

```

<model param range> =::[<modelName>:]<first param> -
                      <last param>
```

See the XSPEC manual for a more detailed description.

The results of the error command are stored in the "error" attributes of the individual Parameter objects.

Examples:

```

# Estimate the 90% confidence ranges for parameters 1-3
  Fit.error("1-3")
# Repeat but with delta fit statistic = 9.0, equivalent to the
# 3 sigma range.
  Fit.error("9.0")
# Estimate for parameter 3 after setting the number of trials to 20.

```

```
# Note that the tolerance field has to be included (or skipped over).
Fit.error("stop 20,,3")
```

### 7.7.3.2 def ftest ( self, chisq2, dof2, chisq1, dof1 )

Calculate the F-statistic and its probability given new and old values of chisq and number of degrees of freedom (DOF).

```
Input:  chisq2 - float
        dof2   - int
        chisq1 - float
        dof1   - int
```

Chisq2 and dof2 should come from a new fit, in which an extra model component was added to (or a frozen parameter thawed from) the model which gave chisq1 and dof1. If the F-test probability is low then it is reasonable to add the extra model component. WARNING: it is not correct to use the F-test statistic to test for the presence of a line (see Protassov et al 2002, ApJ 571, 545).

Returns: The F-test probability [float].

### 7.7.3.3 def goodness ( self, nRealizations = 100, sim = False )

Perform a Monte Carlo calculation of the goodness-of-fit.

\*Available with XSPEC patch 12.7.0a

```
nRealizations -- Number of spectra to simulate [int].
sim           -- If False (default), all simulations are drawn from
                the best fit model parameter values. If True,
                parameters will be drawn from a Gaussian centered
                on the best fit.
```

### 7.7.3.4 def improve ( self )

Try to find a new minimum.

\*Available with XSPEC patch 12.7.0a

When `Fit.method` is set to one of the MINUIT algorithms, this will run the MINUIT 'improve' command. This does nothing when `Fit.method` is set to Levenberg-Marquardt.

#### 7.7.3.5 `def perform ( self )`

Perform fit.

#### 7.7.3.6 `def renorm ( self, setting = None )`

Renormalize the model to minimize statistic with current parameters

`setting` -- If `None`, this will perform an explicit immediate renormalization. Other options determine when renormalization will be performed automatically. They are the following strings:

- "auto" - Renormalize after a model command or parameter change, and at the beginning of a fit.
- "prefit" - Renormalize only at the beginning of a fit.
- "none" - Perform no automatic renormalizations.

#### 7.7.3.7 `def show ( self )`

Show fit information.

#### 7.7.3.8 `def steppar ( self, argString )`

Perform a steppar run.

Generate the statistic "surface" for 1 or more parameters.

Input: `argString` is a string with identical syntax to the standard

```
interactive XSPEC steppar command.  
"<step spec> [<step spec> ...]" where:  
  
    <step spec> ::= [<log|nolog>] [<current|best>]  
    [<modName>:]<param index> <low value> <high value> <# steps>
```

See the XSPEC manual for a more detailed description of specs.

Examples:

```
# Step parameter 3 from 1.5 to 2.5 in 10 linear steps  
Fit.steppar("3 1.5 2.5 10")  
# Repeat the above but with logarithmic steps  
Fit.steppar("log")  
# Step parameter 2 linearly from -.2 to .2 in steps of .02  
Fit.steppar("nolog 2 -.2 .2 20")
```

## 7.7.4 Member Data Documentation

### 7.7.4.1 bayes

Turn Bayesian inference on or off [string].

\*Available with XSPEC patch 12.7.0a

Valid settings are "on", "off" (default), or "cons".  
"cons" turns Bayesian inference on AND gives ALL  
parameters a constant prior. Priors can be set for  
parameters individually through the Parameter object's  
'prior' attribute.

### 7.7.4.2 criticalDelta

Critical delta for fit statistic convergence [float].

The absolute change in the fit statistic between  
iterations, less than which the fit is deemed to  
have converged.

### 7.7.4.3 delta

Set fit delta values to be proportional to the parameter value [float].

Get: Returns the current proportional setting, or 0.0 if currently using the fixed fit delta values.  
Set: Enter the constant factor which will multiply the parameter value to produce a fit delta. A constant factor of 0.0 or negative will turn off the use of proportional fit deltas.

#### 7.7.4.4 dof

The degrees of freedom for the fit [int] (GET only).

#### 7.7.4.5 method

The fitting algorithm to use [string].

Choices are: "leven", "migrad", "minimize", "monte", "simplex". The default is "leven".

When setting the method, additional arguments for <nFitIterations> and <fit critical delta> may also be entered. Valid formats for entering multiple arguments are:

```
# Single string
Fit.method = "migrad 100 .05"
# List of strings
Fit.method = ["migrad", "100", ".05"]
# List of strings and numbers
Fit.method = ["migrad", 100, .05]
```

#### 7.7.4.6 nIterations

The maximum number of fit iterations prior to query [int].

#### 7.7.4.7 query

The fit query setting [string].

```
"yes": Fit will continue through query.  
"no" : Fit will end at query.  
"on" : User will be prompted for "y/n" response.
```

#### 7.7.4.8 statistic

Fit statistic value from the most recent fit [float] (GET only).

#### 7.7.4.9 statMethod

The type of fit statistic in use [string].

```
Valid names: "chi" | "cstat" | "lstat"
```

#### 7.7.4.10 weight

Change the weighting function used in the calculation of chi-sq [string].

```
Available functions: "standard", "gehrels",  
                    "churazov", "model"
```

The documentation for this class was generated from the following file:

- fit.py

## 7.8 Model Class Reference

### Public Member Functions

- def [\\_\\_init\\_\\_](#)
- def [\\_\\_setattr\\_\\_](#)
- def [\\_\\_call\\_\\_](#)
- def [energies](#)



- def [folded](#)
- def [setPars](#)
- def [show](#)
- def [showList](#)
- def [untie](#)
- def [values](#)

#### Public Attributes

- [name](#)  
*The model name, optional in Xspec.*
- [nParameters](#)  
*Number of parameters in [Model](#) object [int].*
- [componentNames](#)  
*List of component name strings.*
- [flux](#)  
*A tuple containing the results of the most recent flux calculation for this model.*
- [lumin](#)  
*Same as flux but for luminosity calculations.*
- [startParIndex](#)  
*Index of the first parameter in this [Model](#) object [int].*

#### 7.8.1 Detailed Description

Xspec model class.

Public instance attributes. Unless stated otherwise, each is get only. flux and lumin are implemented as properties.

```

name          -- The model name, optional in Xspec.
                This is an empty string for un-named models.

<components>  -- Model includes an attribute of type Component for every
                Xspec component in the model. The attribute name is
                the same as the full name of the Xspec component
                (ie. m=Model("po") produces an m.powerlaw
                attribute).

componentNames -- List of component name strings.
```

```

flux          -- A tuple containing the results of the most recent flux
                calculation for this model.

                The tuple values are: (value, errLow, errHigh (in
                ergs/cm^2), value, errLow, errHigh (in photons)).
                This will be filled in after an AllModels.calcFlux()
                call ONLY when no spectra are loaded. Otherwise
                results are stored in the Spectrum objects.

lumin         -- Same as flux but for luminosity calculations.

nParameters   -- Number of parameters in Model object [int].

startParIndex -- Index of the first parameter in this Model object
                [int].

```

### 7.8.2 Constructor & Destructor Documentation

#### 7.8.2.1 `def __init__( self, exprString, modName = "", sourceNum = 1, initPars )`

Model constructor.

New model is automatically added to the AllModels container, with one Model object constructed (internally) for each data group to which the model applies. This function returns the Model object corresponding to the lowest numbered data group.

`exprString` -- The model expression string, components may be abbreviated.

`modName` -- Optional name assigned to model. Any whitespace in string will be removed. This is required if source number is > 1.

`sourceNum` -- Optional integer for model's source number.

Available with XSPEC patch 12.7.0f:

```

**initPars -- Optional initial values for the model's parameters.
            These are entered as an arbitrary number of keyword
            arguments, using the same p<n> keyword syntax as with
            the Model.setPars() method. For example:

```

```

# Create a model with all default parameter settings:
m1 = Model("gauss")

```

```

# Create wabs*powerlaw and initialize pars 1 and 3 to
# something other than their default values.
m2 = Model("wa*po", p1= 5.5, p3=".18,.01,.02")

```

```
# Create another model named 'b', and reset par 2 to 5.0:
m3 = Model("wa*bbody", "b", p2=5.0)
```

If any mistakes are made with the optional `p<n>` parameter arguments, the model will be created using all default values.

You can always reset the parameters later with the `Model.setPars()` method, or directly through the `Parameter` object's `'values'` attribute.

### 7.8.3 Member Function Documentation

#### 7.8.3.1 `def __call__( self, parIdx )`

Get a `Parameter` object from the `Model`.

`parIdx` -- The parameter index number. Note that if there are multiple data groups (and therefore multiple `Model` objects for a given model definition), parameter indices are numbered consecutively ACROSS the multiple `Model` objects. For example, `Model = wabs*powerlaw`:

```
Model object for data group 1:
par      index
nH       1
PhoIndex 2
norm     3
Model object for data group 2:
par      index
nH       4
PhoIndex 5
norm     6
```

Returns the specified `Parameter` object.

#### 7.8.3.2 `def __setattr__( self, attrName, value )`

#### 7.8.3.3 `def energies( self, spectrumIndex )`

Get the `Model` object's energies array for a given spectrum.

spectrumIndex -- The spectrum index number. If this is 0, it will return the energies array used by the default dummy response.

Returns a list of energy array elements, the size will be 1 larger than the corresponding flux array.

This will return the energies array as specified by the AllModels.setEnergies function if that has been used to override the response energies array.

#### 7.8.3.4 def folded ( self, spectrumIndex )

Get the Model object's folded flux array for a given spectrum.

spectrumIndex -- The spectrum index number. This number should be 0 if model is not presently applied to any spectra (ie. in the "off" state).

Returns a list of folded flux array elements.

#### 7.8.3.5 def setPars ( self, seqPars, dictPars )

Change the value of multiple parameters in a single function call.

\*Available with XSPEC patch 12.7.0f

This is a quick way to change multiple parameter values at a time since only a SINGLE model recalculation will be performed at the end. In contrast, when parameter values are changed through the individual parameter objects, the model is recalculated after EACH parameter change.

seqPars -- An arbitrary number of CONSECUTIVE parameter values to be matched 1-to-1 with the model's parameters (see examples below).

dictPars -- An arbitrary number of NON-CONSECUTIVE parameter values, entered with keys: p<n>=<value> (see examples below).

Examples: Assume we have a model object m1 with 5 parameters.

Simplest case: change only the parameter values (and not the auxiliary values, 'sigma', 'min', 'bot', etc.), and change them in consecutive order.

```
# Pass in 1 or more floats
m1.setPars(5.5, 7.83, 4.1e2) # changes pars 1-3
m1.setPars(2.0, 1.3e-5, -.05, 6.34, 9.2) # changes all 5 pars

Still changing only the parameter values, but skipping over some.

m1.setPars(.02, 4.4, p5=3.2e5) # changes pars 1-2, 5
m1.setPars(p2=3.0, p4=-1.2) # changes pars 2, 4

Now also change the auxiliary values for some of the parameters.
Pass in a STRING containing "<val>,<sigma>,<min>,<bottom>,<top>,<max>"
This uses the same syntax as Standard XSPEC's "newpar"
command. Aux values can be skipped by using multiple commas.

# This sets a new <val>, <sigma>, and <max> for parameter 1, and
# a new <val> of 5.3 for parameter 2.
m1.setPars(".3,.01,,,100", 5.3)

# This sets all new auxiliary values for parameter 3.
m1.setPars(p3=".8 -.01 1e-4 1e-3 1e5 1e6")

Change non-consecutive parameters in a model object belonging to
data group 2. Remember that group 2 parameter indices run from
6 to 10, not 1 to 5.

m2 = AllModels(2)
m2.setPars(p6=4.1, p8=3.3, p10=.2)
```

### 7.8.3.6 def show ( self )

Display information for a single Model object.

### 7.8.3.7 def showList ( )

Show the list of all available XSPEC model components.

### 7.8.3.8 def untie ( self )

Remove links for all parameters in Model object

### 7.8.3.9 `def values ( self, spectrumIndex )`

Get the Model object's values array for a given spectrum.

`spectrumIndex` -- The spectrum index number. This number should be 0 if model is not presently applied to any spectra (ie. in the "off" state).

Returns the values array as a list.

## 7.8.4 Member Data Documentation

### 7.8.4.1 `componentNames`

List of component name strings.

### 7.8.4.2 `flux`

A tuple containing the results of the most recent flux calculation for this model.

The tuple values are: (value, errLow, errHigh (in ergs/cm<sup>2</sup>), value, errLow, errHigh (in photons)). This will be filled in after an `AllModels.calcFlux()` call ONLY when no spectra are loaded. Otherwise results are stored in the Spectrum objects.

### 7.8.4.3 `lumin`

Same as flux but for luminosity calculations.

### 7.8.4.4 `name`

The model name, optional in Xspec.

This is an empty string for un-named models.

#### 7.8.4.5 nParameters

Number of parameters in [Model](#) object [int].

#### 7.8.4.6 startParIndex

Index of the first parameter in this [Model](#) object [int].

The documentation for this class was generated from the following file:

- [model.py](#)

## 7.9 ModelManager Class Reference

### Public Member Functions

- [def \\_\\_init\\_\\_](#)
- [def \\_\\_call\\_\\_](#)
- [def \\_\\_iadd\\_\\_](#)
- [def \\_\\_isub\\_\\_](#)
- [def calcFlux](#)
- [def calcLumin](#)
- [def clear](#)
- [def eqwidth](#)
- [def setEnergies](#)
- [def initpackage](#)
- [def lmod](#)
- [def show](#)

### Public Attributes

- [systematic](#)

*The fractional model systematic error.*

#### 7.9.1 Detailed Description

Models container.

This is a singleton - only 1 instance allowed

Public attributes:

```

    systematic      -- The fractional model systematic error.
                     This will be added in quadrature to the error
                     on the data when evaluating chi-squared. The
                     default value is zero.

```

## 7.9.2 Constructor & Destructor Documentation

### 7.9.2.1 `def __init__( self )`

## 7.9.3 Member Function Documentation

### 7.9.3.1 `def __call__( self, groupNum, modName = "" )`

Get Model objects from the AllModels container.

groupNum -- The data group number to which the Model object corresponds.

modName -- Optional string containing the Model's name (if any).

Returns the Model object.

### 7.9.3.2 `def __iadd__( self, modelInfo )`

Define a new model and add it to the AllModels container.

This operation is equivalent to the Model class constructor, except that it does not return a Model object.

modelInfo -- A string containing the model expression (component names may be abbreviated). The model will be unnamed and assigned to source number = 1.

OR

If supplying a model name and a source number, this should be a tuple with:

```

    modelInfo[0] = model expression string

```



```
modelInfo[1] = model name string  
modelInfo[2] = source number
```

### 7.9.3.3 `def __isub__( self, modName )`

Remove all copies of the given model from the AllModels container.

`modName` -- The name of the model to be removed, or an empty string if the model has no name. If set to "\*", this will behave like the `clear()` function and remove all models.

### 7.9.3.4 `def calcFlux( self, cmdStr )`

Calculate the model flux for a given energy range.

`cmdStr` -- A string containing the energy limit values and optional error specifiers. This follows the same syntax rules as the standard XSPEC flux command.

The flux will be calculated for all loaded spectra, and the results will be stored in the Spectrum objects' flux attribute. If no spectra are loaded, the flux will be stored in the Model objects' flux attribute.

### 7.9.3.5 `def calcLumin( self, cmdStr )`

Calculate the model luminosity for a given energy range and redshift.

`cmdStr` -- A string containing the energy limit values and optional error specifiers. This follows the same syntax rules as the standard XSPEC lumin command.

The lumin will be calculated for all loaded spectra, and the results will be stored in the Spectrum objects' lumin attribute. If no spectra are loaded, the flux will be stored in the Model objects' lumin attribute.

### 7.9.3.6 `def clear ( self )`

Remove all models.

### 7.9.3.7 `def eqwidth ( self, component, rangeFrac = None, err = False, number = None, level = None )`

Calculate the equivalent width of a model component.

Please see the Standard XSPEC Manual for a discussion on how the eqwidth of a component is calculated.

`component` -- An integer specifying the model component number for which to calculate the eqwidth (left-most component is 1). If the component belongs to a NAMED model, then this must be a STRING of the form "<modelName>:<compNumber>".

`rangeFrac` -- Determines the energy range for the continuum calculation: from  $E(1-\text{rangeFrac})$  to  $E(1+\text{rangeFrac})$  where  $E$  is the location of the peak of the photon spectrum. The initial default `rangeFrac` is 0.05. Setting this will change the future default value.

`err` -- If set to True, errors will be estimated on the equivalent width calculation. This will also require the setting of the "number" and "level" arguments.

`number` -- Only set this if "err" = True. This determines the number of sets of randomized parameter values to draw to make the error estimation. [int]

`level` -- Only set this if "err" = True. The error algorithm will order the equivalent widths of the <number> sets of parameter values, and the central <level> percent will determine the error range. [float]

The results of the most recent eqwidth calculation are stored as attributes of the currently loaded Spectrum objects.

### 7.9.3.8 `def initpackage ( self, packageName, modDescrFile, dirPath = None, udmget = False )`

Initialize a package of local models.

\*Available with XSPEC patch 12.7.0a

Use this method to compile your local model source code and build a library, which can then be loaded into XSPEC with the 'lmod' method.

```

packageName -- The name of the model package [string].
               The name should be all lower-case and contain NO
               numerals or spaces. The local models library file
               will be based upon this name, and this is also the
               name you will use when loading the library with the
               'lmod' method.

modDescrFile -- Name of your local model description file [string].
               This file is typically named 'lmodel.dat', but you're
               free to name it something else.

dirPath      -- Optional directory path to your local models [string].
               This may be an absolute or relative path. If you
               don't enter this argument, XSPEC will look in the
               directory given by the LOCAL_MODEL_DIRECTORY in your
               Xspec.init start-up file.

udmget       -- Optional flag for when your models need to call XSPEC's
               udmget function [bool]. Udmget is a function for
               allocating dynamic memory in Fortran routines, and
               is no longer used within XSPEC itself. If this
               flag is set to 'True', initpackage will copy the
               necessary files and build the udmget function within
               your local models directory.

```

### 7.9.3.9 def lmod ( self, packageName, dirPath = None )

Load a local models library.

```

packageName -- The name of the model package to be loaded. This
               is the same name that is the first argument in
               the initpackage command.

dirPath      -- An optional string argument specifying the (absolute or
               relative) path to the local model directory. If this
               argument is not entered, Xspec will look in the
               directory given by the LOCAL_MODEL_DIRECTORY in the
               Xspec.init start-up file.

```

### 7.9.3.10 def setEnergies ( self, arg1, arg2 = None )

Specify new energy binning for model fluxes.

Supply an energy binning array to be used in model evaluations in place of the associated response energies, or add an extension to the response energies.

```
arg1 -- A string containing either:
    "<range specifier> [<additional range specifiers>...]"
    "<name of input ascii file>"
    "extend" [This option also uses arg2]
    "reset"
```

```
where the first <range specifier> ::=
    <lowE> <highE> <nBins> log|lin
<additional range specifier> ::= <highE> <nBins> log|lin
This uses the same syntax as standard XSPEC's "energies"
command. Values can be delimited by spaces or commas.
```

```
arg2 -- Only needed when arg1 is "extend", this requires an extension
specifier string of the form:
    "low|high <energy> <nBins> log|lin"
```

All energies are in keV. Multiple ranges may be specified to allow for varied binning in different segments of the array, but note that no gaps are allowed in the overall array. Therefore only the first range specifier accepts a <lowE> parameter. Additional ranges will automatically begin at the <highE> value of the previous range.

With the "extend" option, the specifier string supplied to arg2 will extend the existing response energy array by an additional <nBins> to the new <energy>, in either the high or low direction.

Once an energy array is specified, it will apply to all models and will be used in place of any response energy array (from actual or dummy responses) for calculating and binning the model flux. It will also apply to any models that are created after it is specified. To turn off this behavior and return all models back to using their response energies, set arg1 to "reset".

Arg1 can also be the name of an ascii text file containing a custom energy array. To see the proper file format, and for more details in general about the energies command, please see the standard XSPEC manual.

Examples:

```
# Create an array of 1000 logarithmic-spaced bins, from .1 to 50. keV
AllModels.setEnergies(".1 50. 1000 log")
# Change it to 500 bins
AllModels.setEnergies(",,500")
# Now restore original response energies, but with an extension of the
#   high end to 75.0 keV with 100 additional linear bins.
AllModels.setEnergies("extend","high,75.,100 lin")
# Return to using original response energies with no extensions.
AllModels.setEnergies("reset")
```

### 7.9.3.11 `def show ( self, parIDs = None )`

Show all or a subset of Xspec model parameters.

`parIDs` -- An optional string specifying a range of parameters as with Xspec's "show parameter" function. If no string is supplied, this will show all parameters in all models.

## 7.9.4 Member Data Documentation

### 7.9.4.1 `systematic`

The fractional model systematic error.

This will be added in quadrature to the error on the data when evaluating chi-squared. The default value is zero.

The documentation for this class was generated from the following file:

- `model.py`

## 7.10 Parameter Class Reference

### Public Member Functions

- `def \_\_init\_\_`
- `def untie`
- `def \_\_float\_\_`
- `def \_\_add\_\_`
- `def \_\_radd\_\_`
- `def \_\_iadd\_\_`
- `def \_\_mul\_\_`
- `def \_\_rmul\_\_`
- `def \_\_imul\_\_`

**Public Attributes**

- **name**  
*Name of [Parameter](#) (GET only).*
- **values**  
*List of value floats [val,delta,min,bot,top,max].*
- **sigma**  
*The [Parameter](#) fit sigma (-1.0 when not applicable) (GET only).*
- **frozen**  
*Boolean, if True then parameter is frozen.*
- **link**  
*Link expression string (empty if not linked).*
- **unit**  
*An optional string for the parameter's units (GET only).*
- **error**  
*A tuple containing the results of the most recent fit error command performed on the parameter (GET only).*
- **prior**  
*A tuple containing the settings for the prior used when Bayesian inference is turned on.*

**7.10.1 Detailed Description**

Model parameter class.

Public instance attributes, implemented as properties.

```

name    -- Name of Parameter (GET only).

values  -- List of value floats [val,delta,min,bot,top,max].
          This may be set with:
          string:      x.values = "3.2,,,1e2, 1e3"
          single float: x.values = 4.1 (sets 'val' only)
          tuple:       x.values = 8.2,.02, -10.
          list:        x.values = [8.2,.02, -10.]
          Note that Tuple and List input do not allow the use
          of consecutive commas for argument spacing.

sigma   -- The Parameter fit sigma (-1.0 when not applicable) (GET only).
```

```
frozen -- Boolean, if True then parameter is frozen.

link   -- Link expression string (empty if not linked).

unit   -- An optional string for the parameter's units (GET only).

error  -- A tuple containing the results of the most recent fit error
         command performed on the parameter (GET only).
         The tuple values are: (error low bound, error high bound,
                               error status code string)

prior  -- A tuple containing the settings for the prior used when
         Bayesian inference is turned on.

*Available with XSPEC patch 12.7.0a

Get: Returns a tuple containing:
    (<priorType>, <optional hyperparameters>)

Set with:
    string: <priorType>
    or tuple: (<priorType>, <optional hyperparameters>)
    Valid priorTypes are "cons", "exp", "jeffreys", "gauss".
    Hyperparameters should be entered as floats.
```

## 7.10.2 Constructor & Destructor Documentation

### 7.10.2.1 `def __init__( self, parName )`

Parameter constructor.

`parName` -- Parameter name

## 7.10.3 Member Function Documentation

### 7.10.3.1 `def __add__( self, other )`

### 7.10.3.2 `def __float__( self )`

**7.10.3.3** `def __iadd__ ( self, other )`

**7.10.3.4** `def __imul__ ( self, other )`

**7.10.3.5** `def __mul__ ( self, other )`

**7.10.3.6** `def __radd__ ( self, other )`

**7.10.3.7** `def __rmul__ ( self, other )`

**7.10.3.8** `def untie ( self )`

Remove parameter link (if any)

## **7.10.4 Member Data Documentation**

### **7.10.4.1 error**

A tuple containing the results of the most recent fit error command performed on the parameter (GET only).

The tuple values are: (error low bound, error high bound,  
error status code string)



#### 7.10.4.2 frozen

Boolean, if True then parameter is frozen.

#### 7.10.4.3 link

Link expression string (empty if not linked).

#### 7.10.4.4 name

Name of [Parameter](#) (GET only).

#### 7.10.4.5 prior

A tuple containing the settings for the prior used when Bayesian inference is turned on.

\*Available with XSPEC patch 12.7.0a

Get: Returns a tuple containing:  
(<priorType>, <optional hyperparameters>)

Set with:  
string: <priorType>  
or tuple: (<priorType>, <optional hyperparameters>)  
Valid priorTypes are "cons", "exp", "jeffreys", "gauss".  
Hyperparameters should be entered as floats.

#### 7.10.4.6 sigma

The [Parameter](#) fit sigma (-1.0 when not applicable) (GET only).

#### 7.10.4.7 unit

An optional string for the parameter's units (GET only).

#### 7.10.4.8 values

List of value floats [val,delta,min,bot,top,max].

This may be set with:

```
string:      x.values = "3.2,,,,1e2, 1e3"  
single float: x.values = 4.1 (sets 'val' only)  
tuple:       x.values = 8.2,.02, -10.  
list:        x.values = [8.2,.02, -10.]
```

Note that Tuple and List input do not allow the use of consecutive commas for argument spacing.

The documentation for this class was generated from the following file:

- model.py

## 7.11 PlotManager Class Reference

### Public Member Functions

- def [\\_\\_init\\_\\_](#)
- def [\\_\\_call\\_\\_](#)
- def [addCommand](#)
- def [delCommand](#)
- def [iplot](#)
- def [noID](#)
- def [setGroup](#)
- def [setID](#)
- def [setRebin](#)
- def [show](#)
- def [x](#)
- def [xErr](#)
- def [y](#)
- def [yErr](#)
- def [model](#)
- def [backgroundVals](#)

### Public Attributes

- [add](#)

*Turn on/off the display of individual additive components [bool].*

- [area](#)  
*Toggle displaying the data divided by the response effective area for each channel [bool].*
- [background](#)  
*Toggle displaying the background spectrum (if any) when plotting data [bool].*
- [commands](#)  
*Custom plot commands to be appended to Xspec-generated commands.*
- [device](#)  
*The plotting device name [string].*
- [perHz](#)  
*Toggle displaying Y-axis units per Hz when using wavelength units for X-axis [bool].*
- [redshift](#)  
*Apply a redshift to the X-axis energy or wavelength values [float].*
- [splashPage](#)  
*When set to False, the usual XSPEC version and build data information will not be printed to the screen when the first plot window is initially opened [bool].*
- [xAxis](#)  
*X-Axis Units [string].*
- [xLog](#)  
*Set the x-axis to logarithmic or linear for energy or wavelength plots [bool].*
- [yLog](#)  
*See xLog.*

### 7.11.1 Detailed Description

Xspec plotting class.

This is a singleton - only 1 instance allowed

Public instance attributes:

```
add          -- Turn on/off the display of individual additive
               components [bool].

area         -- Toggle displaying the data divided by the response
```

```

        effective area for each channel [bool].

background -- Toggle displaying the background spectrum (if any)
              when plotting data [bool].

commands    -- Custom plot commands to be appended to Xspec-generated
              commands.

              Get: Returns a tuple of the currently entered command
                  strings.
              Set: Replaces all commands with the new tuple of
                  strings.

              To remove ALL plot commands, set to an empty tuple, ie:
                  Plot.commands = ()

              For inserting and deleting individual commands, use
                  addCommand and delCommand functions.

device      -- The plotting device name [string].

perHz       -- Toggle displaying Y-axis units per Hz when using
              wavelength units for X-axis [bool].

redshift    -- Apply a redshift to the X-axis energy or wavelength
              values [float].
              This will multiply X-axis energies by a factor of (1+z)
              to allow for viewing in the source frame. Y-axis values
              will be equally affected in plots which are normalized
              by energy or wavelength. Note that this is not
              connected in any way to redshift parameters in the model
              (or the setplot id redshift parameter) and should only
              be used for illustrative purposes.

splashPage -- When set to False, the usual XSPEC version and build data
              information will not be printed to the screen when the
              first plot window is initially opened [bool].

xAxis       -- X-Axis Units [string].
              Valid options are:  "channel"
                                (energies)  "keV", "MeV", "GeV", "Hz"
                                (wavelengths) "angstrom", "cm", "micron", "nm"

              These are case-insensitive and may be abbreviated.

              This setting also affects the ignore/notice range
              interpretation.

xLog        -- Set the x-axis to logarithmic or linear for energy or
              wavelength plots [bool].

              xLog has no effect on plots in channel space. xLog
              and yLog will not work for model-related plots
              (eg. model, ufspec, and their variants) as their axes
              are always set to log scale.

yLog        -- See xLog.

```

### 7.11.2 Constructor & Destructor Documentation

#### 7.11.2.1 `def __init__ ( self, deviceStr )`

### 7.11.3 Member Function Documentation

#### 7.11.3.1 `def __call__ ( self, panes )`

Display the plot.

Input 1 or more plot command strings.

Examples:

```
Single Plots:
Plot("data")
Plot("model")
Plot("ufspec")
```

```
Multiple Plots (or single plots taking additional arguments):
Plot("data","model","resid")
Plot("data model resid")
Plot("data,model,resid")
Plot("data","model m1") # Plots data and a model named "m1".
```

To repeat a plot using the previously entered arguments,  
simply do: `Plot()`

#### 7.11.3.2 `def addCommand ( self, cmd )`

Add a plot command [string] to the end of the plot commands list.

#### 7.11.3.3 `def backgroundVals ( self, plotGroup = 1 )`

Return a list of background data values for a plot group

Background value arrays only exist for data plots when the `Plot.background` flag is set to `True`.

#### 7.11.3.4 `def delCommand ( self, num )`

Remove a plot command by (1-based) number [int].

This is intended for removal of single commands. To remove ALL commands, set the `Plot.commands` attribute to an empty tuple, ie:  
`Plot.commands = ()`

#### 7.11.3.5 `def iplot ( self, panes )`

Display the plot and leave it in interactive plotting mode.

This function takes the same arguments and syntax as when displaying plots in the regular mode (through `Plot's __call__` method). Examples:

```
Plot.iplot("data")      # 1-panel data plot
Plot.iplot("data model") # 2-panel data and model
Plot.iplot()            # Repeats the previous plot.
```

#### 7.11.3.6 `def model ( self, plotGroup = 1 )`

Return a list of Y-coordinate model values for a plot group

#### 7.11.3.7 `def noID ( self )`

Turn off the plotting of line IDs.

**7.11.3.8 def setGroup ( self, groupStr )**

Define a range of spectra to be in the same plot group.

Input argument is a string specifying one or more ranges, delimited by commas and/or spaces.

Examples:

```
"1-3 4-6" : Spectra 1-3 in plot group 1, 4-6 in group 2.
"1,2 4"   : Spectra 1, 2, and 4 are each now in their own group.
"1-**"    : All spectra are in a single plot group.
```

```
None      : If input argument is Python's None variable, all
            plot grouping will be removed.
```

**7.11.3.9 def setID ( self, temperature = None, emissivity = None, redshift = None )**

Switch on plotting of line IDs.

All input arguments are floats and are optional. If they are omitted they will retain their previous values.

```
temperature -- Selects the temperature of the APEC line list.
emissivity  -- Only lines with emissivities above this setting will
               be displayed.
redshift    -- Line display will be redshifted by this amount.
```

To turn off plotting of line IDs, use the noID() function.

**7.11.3.10 def setRebin ( self, minSig = None, maxBins = None, groupNum = None, errType = None )**

Define characteristics used in rebinning the data (for plotting purposes ONLY).

All input arguments are optional. If they are omitted they will retain their previous values.

```
minSig  -- Bins will be combined until this minimum significance
           is reached (in units of sigma). [float]
maxBins -- The maximum number of bins to combine in attempt to
           reach minSig. [int]
```

```
groupNum -- The plot group number to which this setting applies.  
           If number is negative, it will apply to ALL plot  
           groups. [int]  
errType  -- Specifies how to calculate the error bars on the new  
           bins. Valid entries are "quad", "sqrt", "poiss-1",  
           "poiss-2", "poiss-3". [string] See the "setplot"  
           description in the XSPEC manual for more information.
```

#### 7.11.3.11 `def show ( self )`

Display current plot settings

#### 7.11.3.12 `def x ( self, plotGroup = 1 )`

Return a list of X-coordinate data values for a plot group

#### 7.11.3.13 `def xErr ( self, plotGroup = 1 )`

Return a list of X-coordinate errors for a plot group

#### 7.11.3.14 `def y ( self, plotGroup = 1 )`

Return a list of Y-coordinate data values for a plot group

#### 7.11.3.15 `def yErr ( self, plotGroup = 1 )`

Return a list of Y-coordinate errors for a plot group



#### 7.11.4 Member Data Documentation

##### 7.11.4.1 add

Turn on/off the display of individual additive components [bool].

##### 7.11.4.2 area

Toggle displaying the data divided by the response effective area for each channel [bool].

##### 7.11.4.3 background

Toggle displaying the background spectrum (if any) when plotting data [bool].

##### 7.11.4.4 commands

Custom plot commands to be appended to Xspec-generated commands.

Get: Returns a tuple of the currently entered command strings.

Set: Replaces all commands with the new tuple of strings.

To remove ALL plot commands, set to an empty tuple, ie:  
`Plot.commands = ()`

For inserting and deleting individual commands, use  
`addCommand` and `delCommand` functions.

##### 7.11.4.5 device

The plotting device name [string].

#### 7.11.4.6 perHz

Toggle displaying Y-axis units per Hz when using wavelength units for X-axis [bool].

#### 7.11.4.7 redshift

Apply a redshift to the X-axis energy or wavelength values [float].

```
This will multiply X-axis energies by a factor of (1+z)
to allow for viewing in the source frame. Y-axis values
will be equally affected in plots which are normalized
by energy or wavelength. Note that this is not
connected in any way to redshift parameters in the model
(or the setplot id redshift parameter) and should only
be used for illustrative purposes.
```

#### 7.11.4.8 splashPage

When set to False, the usual XSPEC version and build data information will not be printed to the screen when the first plot window is initially opened [bool].

#### 7.11.4.9 xAxis

X-Axis Units [string].

```
Valid options are:  "channel"
                    (energies)  "keV", "MeV", "GeV", "Hz"
                    (wavelengths) "angstrom", "cm", "micron", nm"
These are case-insensitive and may be abbreviated.
This setting also affects the ignore/notice range
interpretation.
```

#### 7.11.4.10 xLog

Set the x-axis to logarithmic or linear for energy or wavelength plots [bool].

xLog has no effect on plots in channel space. xLog and yLog will not work for model-related plots (eg. model, ufspec, and their variants) as their axes are always set to log scale.

#### 7.11.4.11 yLog

See xLog.

The documentation for this class was generated from the following file:

- plot.py

## 7.12 Response Class Reference

### Public Member Functions

- def [\\_\\_init\\_\\_](#)

### Public Attributes

- [arf](#)  
*Get/Set the arf filename string.*
- [chanEnergies](#)  
*Tuple of floats, the detector channel energies in keV.*
- [energies](#)  
*Tuple of floats, the photon energies in keV which are stored in the MATRIX extension.*
- [rmf](#)  
*The response file name string.*
- [sourceNumber](#)  
*The 1-based source number for which the response is assigned.*

### 7.12.1 Detailed Description

Detector response class.

Public instance attributes implemented as properties, these are GET only unless specified otherwise.

```
arf          -- Get/Set the arf filename string.  
               Enter None or empty string to remove an existing arf.  
  
chanEnergies -- Tuple of floats, the detector channel energies in keV.  
               These are the energies normally stored in the  
               EBOUNDS extension.  
  
energies     -- Tuple of floats, the photon energies in keV which are  
               stored in the MATRIX extension.  
  
rmf          -- The response file name string.  
  
sourceNumber -- The 1-based source number for which the response is  
               assigned.  
               This is normally always 1 unless multiple sources are  
               loaded for multiple-model evaluation.
```

### 7.12.2 Constructor & Destructor Documentation

#### 7.12.2.1 `def __init__( self, respTuple )`

Construct a Response object.

Intended for creation by a Spectrum object only.

### 7.12.3 Member Data Documentation

#### 7.12.3.1 `arf`

Get/Set the arf filename string.

Enter None or empty string to remove an existing arf.

#### 7.12.3.2 `chanEnergies`

Tuple of floats, the detector channel energies in keV.

```
These are the energies normally stored in the  
EBOUNDS extension.
```

#### 7.12.3.3 energies

Tuple of floats, the photon energies in keV which are stored in the MATRIX extension.

#### 7.12.3.4 rmf

The response file name string.

#### 7.12.3.5 sourceNumber

The 1-based source number for which the response is assigned.

```
This is normally always 1 unless multiple sources are  
loaded for multiple-model evaluation.
```

The documentation for this class was generated from the following file:

- response.py

## 7.13 Spectrum Class Reference

### Public Member Functions

- def [\\_\\_init\\_\\_](#)
- def [dummyrsp](#)
- def [ignore](#)
- def [notice](#)
- def [noticedString](#)
- def [show](#)

**Public Attributes**

- [areaScale](#)  
*The [Spectrum](#) area scaling factor.*
- [background](#)  
*Get/Set the spectrum's background.*
- [cornorm](#)  
*Get/Set the normalization of a spectrum's correction file [float].*
- [correction](#)  
*Get/Set the correction file.*
- [dataGroup](#)  
*The data group to which the spectrum belongs [int].*
- [energies](#)  
*Tuple of pairs of floats (also implemented as tuples) giving the E\_Min and E\_Max of each noticed channel.*
- [eqwidth](#)  
*Tuple of 3 floats containing the results of the most recent eqwidth calculation for this spectrum (performed with the [AllModels.eqwidth](#) method).*
- [exposure](#)  
*The exposure time keyword value [float].*
- [fileName](#)  
*The spectrum's file name [string].*
- [flux](#)  
*A tuple containing the results of the most recent flux calculation for this spectrum.*
- [index](#)  
*The spectrum's current index number within the [AllData](#) container [int].*
- [isPoisson](#)  
*Boolean flag, true if spectrum has Poisson errors.*
- [lumin](#)  
*Similar to flux, the results of the most recent luminosity calculation.*

- [multiresponse](#)

*Get/Set detector response ARRAY elements when using multiple sources.*

- [noticed](#)

*A list of the currently noticed (1-based) channel numbers.*

- [rate](#)

*A tuple containing the total [Spectrum](#) rates in counts/sec.*

- [response](#)

*Get/Set the detector response.*

- [values](#)

*Tuple of floats containing the spectrum rates for noticed channels in counts/cm<sup>2</sup>-sec.*

- [variance](#)

*Tuple of floats containing the variance of each noticed channel.*

### 7.13.1 Detailed Description

Spectral data class.

Public instance attributes (implemented as properties). Unless stated otherwise, each is GET only.

```

areaScale -- The Spectrum area scaling factor.
             Either a single float (if file stores it as a keyword),
             or a Tuple of floats (if file stores column).

background -- Get/Set the spectrum's background.

             Get: Returns the Background object associated with the
                   Spectrum. If Spectrum has no background object,
                   this will raise an Exception.

             Set: Supply a background filename [string].
                   This will become the new background to the Spectrum
                   object, and any previously existing background will
                   be removed. If string is empty, all whitespace,
                   or the Python None variable, the background (if
                   any) will be removed.

cornorm    -- Get/Set the normalization of a spectrum's correction file
             [float].

correction -- Get/Set the correction file.

             Get: Returns the Spectrum's current correction information
                   as an object of class Background. This raises an

```

```

        Exception if Spectrum has no correction.

    Set: Enter the filename string for the new correction.
        This will remove any previously existing
        correction. Returns the new correction info
        as an object of class Background.
        If string is "none", empty, or all whitespace,
        the current correction will be removed and this
        will return None.

    dataGroup -- The data group to which the spectrum belongs [int].

    energies -- Tuple of pairs of floats (also implemented as tuples)
        giving the E_Min and E_Max of each noticed channel.

    eqwidth -- Tuple of 3 floats containing the results of the most recent
        eqwidth calculation for this spectrum (performed with the
        AllModels.eqwidth method).

        The results are stored as:
            [0] - eqwidth calculation
            [1] - eqwidth error lower bound
            [2] - eqwidth error upper bound
        The error bounds will be 0.0 if no error calculation was
        performed, and all will be 0.0 if eqwidth wasn't
        performed for this spectrum.

    exposure -- The exposure time keyword value [float].

    fileName -- The spectrum's file name [string].

    flux -- A tuple containing the results of the most recent flux
        calculation for this spectrum.

        The tuple values are:
        (value, errLow, errHigh (in ergs/cm^2), value, errLow,
        errHigh (in photons)) for each model applied to the
        spectrum.

    index -- The spectrum's current index number within the AllData
        container [int].

    isPoisson -- Boolean flag, true if spectrum has Poisson errors.

    lumin -- Similar to flux, the results of the most recent luminosity
        calculation.

    multiresponse -- Get/Set detector response ARRAY elements when
        using multiple sources.

        This is for use only when assigning multiple responses
        to a spectrum, for multi-source/multi-model analysis.
        For standard single-source analysis, use the
        "response" attribute instead.

        You must provide an array index for all multiresponse
        get/set operations. Note that array indices ARE 0-BASED,

```



```

so multiresponse[0] corresponds to source 1. Examples:

# Get the response assigned to source 1.
# This particular call is the same as doing
# "r1 = s.response"
r1 = spec.multiresponse[0]

# Get the response for the second source.
# Can only do this with multiresponse.
r2 = spec.multiresponse[1]

# Define a third source by adding a new response:
spec.multiresponse[2] = "myResp3.pha"

# Now remove the response for the second source:
spec.multiresponse[1] = None

noticed  -- A list of the currently noticed (1-based) channel numbers.

rate      -- A tuple containing the total Spectrum rates in counts/sec.

            The tuple consists of:
            [0] - current net rate (w/ background subtracted),
            [1] - net rate variance,
            [2] - total rate (without background),
            [3] - predicted model rate

response  -- Get/Set the detector response.

            Use this for standard SINGLE-SOURCE analysis.
            To add other responses for multi-source and multi-model
            analysis, use the "multiresponse" attribute.

            Get: Returns a Response object, or raises an
                  Exception if none exists

            Set: Supply a response filename string. To remove
                  a response, supply an empty string or None.

values    -- Tuple of floats containing the spectrum rates for noticed
            channels in counts/cm^2-sec.

variance  -- Tuple of floats containing the variance of each noticed
            channel.

```

## 7.13.2 Constructor & Destructor Documentation

### 7.13.2.1 `def __init__( self, dataFile )`

Construct a Spectrum object.

Read in a spectrum and any associated background, response and arf files. Spectrum is automatically added to the AllData container.

dataFile - Spectral data filename [string].

### 7.13.3 Member Function Documentation

**7.13.3.1** `def dummyrsp ( self, lowE = None, highE = None, nBins = None, scaleType = None, chanOffset = None, chanWidth = None, sourceNum = 1 )`

Create a dummy response for this spectrum only.

Input arguments, all are optional:

lowE - Input response energy lower bound, in keV. [float]  
 highE - Input response energy higher bound, in keV. [float]  
 nBins - Number of bins into which the energy range is divided [int].  
 scaleType - "log" or "lin" [string]  
 chanOffset - Starting value of dummy channel energies. [float]  
 chanWidth - Energy width of the channel bins. [float]  
     If this is set to 0, the dummy response  
     can only be used for evaluating model arrays,  
     and not for fitting to spectra.  
 sourceNum - Optional source number for the dummy response. [int]

Examples:

```
# All values are optional, use keywords to enter values
# non-consecutively. Unspecified values revert to the
# current defaults.
s = Spectrum("dataFile.pha")
s.dummyrsp(.3, 30., 100, chanWidth=.5)
s.dummyrsp(highE = 50., sourceNum = 2)
s.dummyrsp(.1,10.,100,"lin",.0, 1.0, 1)
```

Initial defaults: lowE = .1, highE = 50., nBins = 50, scaleType = "log"  
 chanOffset = .0, chanWidth = .0, sourceNum = 1  
 The defaults for lowE, highE, nBins, scaleType, and chanOffset will be  
 modified for each explicit new entry. chanWidth always defaults to 0  
 and sourceNum always defaults to 1.

To remove the spectrum's dummy response(s) and restore actual  
 responses (if any), call AllData.removeDummyrsp().

### 7.13.3.2 `def ignore ( self, ignoreRange )`

Ignore a range of the spectrum by channels or energy/wavelengths.

`ignoreRange` -- String specifying the channel range to ignore. This follows the same syntax as used in the standard Xspec "ignore" command. If the numbers are floats rather than ints, they will be treated as energies or wavelengths (depending on the Plot settings).

Note that "bad" will not work from here, as it can only be applied to ALL of the loaded spectra.

To apply range(s) to multiple spectra, use the `AllData ignore` function.

### 7.13.3.3 `def notice ( self, noticeRange )`

Notice a range of the spectrum by channels or energy/wavelengths.

`noticeRange` -- String specifying the channel range to notice. This follows the same syntax as used in the standard Xspec "notice" command. If the numbers are floats rather than ints, they will be treated as energies or wavelengths (depending on the Plot settings). If the string is "all", it will notice all channels in spectrum.

To apply range(s) to multiple spectra, use the `AllData notice` function.

### 7.13.3.4 `def noticedString ( self )`

Return a string of noticed channel ranges.

This produces a string in compact (hyphenated) form, which can be used as input to a subsequent 'notice' command. Example:

```
If noticed channels are [1,3,4,5,7],
this will output "1 3-5 7".
```

### 7.13.3.5 `def show ( self )`

Display information for this Spectrum object

## 7.13.4 Member Data Documentation

### 7.13.4.1 `areaScale`

The [Spectrum](#) area scaling factor.

Either a single float (if file stores it as a keyword),  
or a Tuple of floats (if file stores column).

### 7.13.4.2 `background`

Get/Set the spectrum's background.

Get: Returns the Background object associated with the  
Spectrum. If Spectrum has no background object,  
this will raise an Exception.

Set: Supply a background filename [string].  
This will become the new background to the Spectrum  
object, and any previously existing background will  
be removed. If string is empty, all whitespace,  
or the Python None variable, the background (if  
any) will be removed.

### 7.13.4.3 `cornorm`

Get/Set the normalization of a spectrum's correction file [float].

### 7.13.4.4 `correction`

Get/Set the correction file.

**Get:** Returns the Spectrum's current correction information as an object of class Background. This raises an Exception if Spectrum has no correction.

**Set:** Enter the filename string for the new correction. This will remove any previously existing correction. Returns the new correction info as an object of class Background. If string is "none", empty, or all whitespace, the current correction will be removed and this will return None.

#### 7.13.4.5 dataGroup

The data group to which the spectrum belongs [int].

#### 7.13.4.6 energies

Tuple of pairs of floats (also implemented as tuples) giving the E\_Min and E\_Max of each noticed channel.

#### 7.13.4.7 eqwidth

Tuple of 3 floats containing the results of the most recent eqwidth calculation for this spectrum (performed with the AllModels.eqwidth method).

The results are stored as:

- [0] - eqwidth calculation
- [1] - eqwidth error lower bound
- [2] - eqwidth error upper bound

The error bounds will be 0.0 if no error calculation was performed, and all will be 0.0 if eqwidth wasn't performed for this spectrum.

#### 7.13.4.8 exposure

The exposure time keyword value [float].

#### 7.13.4.9 fileName

The spectrum's file name [string].

#### 7.13.4.10 flux

A tuple containing the results of the most recent flux calculation for this spectrum.

The tuple values are:  
(value, errLow, errHigh (in ergs/cm<sup>2</sup>), value, errLow,  
errHigh (in photons)) for each model applied to the  
spectrum.

#### 7.13.4.11 index

The spectrum's current index number within the AllData container [int].

#### 7.13.4.12 isPoisson

Boolean flag, true if spectrum has Poisson errors.

#### 7.13.4.13 lumin

Similar to flux, the results of the most recent luminosity calculation.

#### 7.13.4.14 multiresponse

Get/Set detector response ARRAY elements when using multiple sources.

This is for use only when assigning multiple responses  
to a spectrum, for multi-source/multi-model analysis.  
For standard single-source analysis, use the  
"response" attribute instead.

You must provide an array index for all multiresponse get/set operations. Note that array indices ARE 0-BASED, so multiresponse[0] corresponds to source 1. Examples:

```
# Get the response assigned to source 1.
# This particular call is the same as doing
# "r1 = s.response"
r1 = spec.multiresponse[0]
# Get the response for the second source.
# Can only do this with multiresponse.
r2 = spec.multiresponse[1]
# Define a third source by adding a new response:
spec.multiresponse[2] = "myResp3.pha"
# Now remove the response for the second source:
spec.multiresponse[1] = None
```

#### 7.13.4.15 noticed

A list of the currently noticed (1-based) channel numbers.

#### 7.13.4.16 rate

A tuple containing the total [Spectrum](#) rates in counts/sec.

The tuple consists of:

- [0] - current net rate (w/ background subtracted),
- [1] - net rate variance,
- [2] - total rate (without background),
- [3] - predicted model rate

#### 7.13.4.17 response

Get/Set the detector response.

Use this for standard SINGLE-SOURCE analysis.  
To add other responses for multi-source and multi-model analysis, use the "multiresponse" attribute.

Get: Returns a Response object, or raises an  
Exception if none exists

Set: Supply a response filename string. To remove

a response, supply an empty string or None.

#### 7.13.4.18 values

Tuple of floats containing the spectrum rates for noticed channels in counts/cm<sup>2</sup>-sec.

#### 7.13.4.19 variance

Tuple of floats containing the variance of each noticed channel.

The documentation for this class was generated from the following file:

- spectrum.py

## 7.14 XspecSettings Class Reference

### Public Member Functions

- def `__init__`
- def `addModelString`
- def `delModelString`
- def `closeLog`
- def `openLog`
- def `show`

### Public Attributes

- `abund`  
*Get/Set the abundance table used in the plasma emission and photoelectric absorption models [string].*
- `allowNewAttributes`  
*Get/Set the flag which allows the setting of new instance attributes for ALL PyXspec classes [bool].*
- `chatter`  
*Get/Set the console chatter level [int].*



- [logChatter](#)

*Get/Set the log chatter level [int].*

- [cosmo](#)

*Get/Set the cosmology values.*

- [log](#)

*Get only: Returns the currently opened log file object, or None if no log file is open (also see the openLog and closeLog methods).*

- [modelStrings](#)

*XSPEC's internal database of <string\_name>, <string\_value> pairs for settings which may be accessed by model functions.*

- [seed](#)

*Re-seed and re-initialize XSPEC's random-number generator with the supplied integer value (SET only).*

- [version](#)

*The version strings for PyXspec and standard XSPEC.*

- [xspect](#)

*Change the photoelectric absorption cross-sections in use [string].*

### 7.14.1 Detailed Description

Storage class for Xspec settings.

This is a singleton - only 1 instance allowed

Public instance attributes (implemented as properties):

`abund`      `--` Get/Set the abundance table used in the plasma emission and photoelectric absorption models [string].

Valid tables: angr, aspl, feld, aneb, grsa, wilm, lodd,  
file <filename>

`allowNewAttributes` `--` Get/Set the flag which allows the setting of new instance attributes for ALL PyXspec classes [bool].

This is False by default, and is intended to catch the user's attention if they misspell an attribute name when attempting to set it. Under normal Python behavior, a misspelling would simply create a new attribute and issue no warnings or errors.

You must make sure this flag is set to True if you genuinely wish to add new attributes.

chatter -- Get/Set the console chatter level [int].  
logChatter -- Get/Set the log chatter level [int].

cosmo -- Get/Set the cosmology values.

Get: Returns a tuple of floats containing (H0, q0, l0), where H0 is the Hubble constant in km/(s-Mpc), q0 is the deceleration parameter, and l0 is the cosmological constant.

Set: Enter a single string containing one or more of H0, q0, l0. Examples:

```
Xset.cosmo = "100" # sets H0 to 100.0
Xset.cosmo = ",0" # sets q0 to 0.0
Xset.cosmo = ",,0.7" # sets l0 to 0.7
Xset.cosmo = "50 .5 0." # sets H0=50.0, q0=0.5, l0=0.0
```

log -- Get only: Returns the currently opened log file object, or None if no log file is open (also see the openLog and closeLog methods).

modelStrings -- XSPEC's internal database of <string\_name>, <string\_value> pairs for settings which may be accessed by model functions.

Get: Returns a tuple of tuples, the inner tuples being composed of <string\_name>, <string\_value> string pairs.

Set: Replaces ENTIRE database with user-supplied new database. Input may be a dictionary of <string\_name>:<string\_value> entries, or a tuple of (<string\_name>, <string\_value>) tuples.

For inserting and deleting INDIVIDUAL string name and value pairs, use the addModelString and delModelString methods.

seed -- Re-seed and re-initialize XSPEC's random-number generator with the supplied integer value (SET only).

version -- The version strings for PyXspec and standard XSPEC.  
GET only, this returns a tuple containing:  
[0] - The PyXspec version string  
[1] - Standard XSPEC's version string

xsect -- Change the photoelectric absorption cross-sections in use [string].

Available options: "bcmc", "obcm", "vern"

### 7.14.2 Constructor & Destructor Documentation

#### 7.14.2.1 `def __init__ ( self )`

### 7.14.3 Member Function Documentation

#### 7.14.3.1 `def addModelString ( self, key, value )`

Add a key,value pair of strings to XSPEC's internal database.

This database provides a way to pass string values to certain model functions which are hardcoded to search for "key".  
(See the XSPEC manual description for the "xset" command for a table showing model/key usage.)

If the key,value pair already exists, it will be replaced with the new entries.

#### 7.14.3.2 `def closeLog ( self )`

Close Xspec's current log file.

#### 7.14.3.3 `def delModelString ( self, key )`

Remove a key,value pair from XSPEC's internal string database.

#### 7.14.3.4 `def openLog ( self, fileName )`

Open a file and set it to be Xspec's log file.

fileName -- The name of the log file.

If Xspec already has an open log file, it will close it.

Returns a Python file object for the new log file.

Once opened, the log file object is also stored as the Xset.log attribute.

#### 7.14.3.5 `def show ( self )`

### 7.14.4 Member Data Documentation

#### 7.14.4.1 `abund`

Get/Set the abundance table used in the plasma emission and photoelectric absorption models [string].

Valid tables: angr, aspl, feld, aneb, grsa, wilm, lodd,  
file <filename>

#### 7.14.4.2 `allowNewAttributes`

Get/Set the flag which allows the setting of new instance attributes for ALL PyXspec classes [bool].

This is False by default, and is intended to catch the user's attention if they misspell an attribute name when attempting to set it. Under normal Python behavior, a misspelling would simply create a new attribute and issue no warnings or errors.

You must make sure this flag is set to True if you genuinely wish to add new attributes.

#### 7.14.4.3 `chatter`

Get/Set the console chatter level [int].

#### 7.14.4.4 cosmo

Get/Set the cosmology values.

Get: Returns a tuple of floats containing (H0, q0, l0), where  
H0 is the Hubble constant in km/(s-Mpc),  
q0 is the deceleration parameter, and  
l0 is the cosmological constant.

Set: Enter a single string containing one or more of  
H0, q0, l0. Examples:

```
Xset.cosmo = "100" # sets H0 to 100.0
Xset.cosmo = ",0" # sets q0 to 0.0
Xset.cosmo = ",,0.7" # sets l0 to 0.7
Xset.cosmo = "50 .5 0." # sets H0=50.0, q0=0.5, l0=0.0
```

#### 7.14.4.5 log

Get only: Returns the currently opened log file object, or None if no log file is open (also see the openLog and closeLog methods).

#### 7.14.4.6 logChatter

Get/Set the log chatter level [int].

#### 7.14.4.7 modelStrings

XSPEC's internal database of <string\_name>, <string\_value> pairs for settings which may be accessed by model functions.

Get: Returns a tuple of tuples, the inner tuples  
being composed of <string\_name>, <string\_value>  
string pairs.

Set: Replaces ENTIRE database with user-supplied  
new database. Input may be a dictionary of  
<string\_name>:<string\_value> entries, or a tuple  
of (<string\_name>, <string\_value>) tuples.

For inserting and deleting INDIVIDUAL string name and value pairs, use the addModelString and delModelString methods.

#### 7.14.4.8 seed

Re-seed and re-initialize XSPEC's random-number generator with the supplied integer value (SET only).

#### 7.14.4.9 version

The version strings for PyXspec and standard XSPEC.

GET only, this returns a tuple containing:  
[0] - The PyXspec version string  
[1] - Standard XSPEC's version string

#### 7.14.4.10 xsect

Change the photoelectric absorption cross-sections in use [string].

Available options: "bcmc", "obcm", "vern"

The documentation for this class was generated from the following file:

- xset.py

## Index

- `__add__`
  - `model::Parameter`, 76
- `__call__`
  - `chain::ChainManager`, 39
  - `data::DataManager`, 44
  - `model::Model`, 64
  - `model::ModelManager`, 69
  - `plot::PlotManager`, 82
- `__float__`
  - `model::Parameter`, 76
- `__iadd__`
  - `chain::ChainManager`, 39
  - `data::DataManager`, 44
  - `model::ModelManager`, 69
  - `model::Parameter`, 76
- `__imul__`
  - `model::Parameter`, 77
- `__init__`
  - `chain::Chain`, 35
  - `chain::ChainManager`, 39
  - `data::DataManager`, 44
  - `data::FakeitSettings`, 51
  - `fit::FitManager`, 56
  - `model::Component`, 42
  - `model::Model`, 63
  - `model::ModelManager`, 69
  - `model::Parameter`, 76
  - `plot::PlotManager`, 82
  - `response::Response`, 89
  - `spectrum::Background`, 32
  - `spectrum::Spectrum`, 94
  - `xset::XspecSettings`, 104
- `__isub__`
  - `chain::ChainManager`, 40
  - `data::DataManager`, 45
  - `model::ModelManager`, 70
- `__mul__`
  - `model::Parameter`, 77
- `__radd__`
  - `model::Parameter`, 77
- `__rmul__`
  - `model::Parameter`, 77
- `__setattr__`
  - `model::Component`, 43
  - `model::Model`, 64
- `abund`
  - `xset::XspecSettings`, 105
- `add`
  - `plot::PlotManager`, 86
- `addCommand`
  - `plot::PlotManager`, 82
- `addModelString`
  - `xset::XspecSettings`, 104
- `allowNewAttributes`
  - `xset::XspecSettings`, 105
- `area`
  - `plot::PlotManager`, 86
- `areaScale`
  - `spectrum::Background`, 33
  - `spectrum::Spectrum`, 97
- `arf`
  - `data::FakeitSettings`, 52
  - `response::Response`, 89
- `backExposure`
  - `data::FakeitSettings`, 52
- `background`
  - `data::FakeitSettings`, 52
  - `plot::PlotManager`, 86
  - `spectrum::Spectrum`, 97
- `backgroundVals`
  - `plot::PlotManager`, 82
- `bayes`
  - `fit::FitManager`, 59
- `burn`
  - `chain::Chain`, 36
- `calcFlux`
  - `model::ModelManager`, 70
- `calcLumin`
  - `model::ModelManager`, 70
- `chain::Chain`, 34
  - `__init__`, 35
  - `burn`, 36
  - `fileName`, 36

- fileType, 36
- proposal, 36
- rand, 37
- run, 36
- runLength, 37
- show, 36
- temperature, 37
- totalLength, 37
- chain::ChainManager, 38
  - \_\_call\_\_, 39
  - \_\_iadd\_\_, 39
  - \_\_init\_\_, 39
  - \_\_isub\_\_, 40
  - clear, 40
  - defBurn, 41
  - defFileType, 41
  - defLength, 41
  - defProposal, 41
  - defRand, 41
  - defTemperature, 41
  - show, 40
  - stat, 40
- chanEnergies
  - response::Response, 89
- chatter
  - xset::XspecSettings, 105
- clear
  - chain::ChainManager, 40
  - data::DataManager, 45
  - model::ModelManager, 70
- closeLog
  - xset::XspecSettings, 104
- commands
  - plot::PlotManager, 86
- componentNames
  - model::Model, 67
- cornorm
  - spectrum::Spectrum, 97
- correction
  - data::FakeitSettings, 52
  - spectrum::Spectrum, 97
- cosmo
  - xset::XspecSettings, 105
- criticalDelta
  - fit::FitManager, 59
- data::DataManager, 43
  - \_\_call\_\_, 44
  - \_\_iadd\_\_, 44
  - \_\_init\_\_, 44
  - \_\_isub\_\_, 45
  - clear, 45
  - diagsrp, 45
  - dummyrsp, 45
  - fakeit, 46
  - ignore, 48
  - nGroups, 49
  - notice, 48
  - nSpectra, 49
  - removeDummyrsp, 49
  - show, 49
- data::FakeitSettings, 49
  - \_\_init\_\_, 51
  - arf, 52
  - backExposure, 52
  - background, 52
  - correction, 52
  - exposure, 52
  - fileName, 53
  - response, 53
- dataGroup
  - spectrum::Spectrum, 98
- defBurn
  - chain::ChainManager, 41
- defFileType
  - chain::ChainManager, 41
- defLength
  - chain::ChainManager, 41
- defProposal
  - chain::ChainManager, 41
- defRand
  - chain::ChainManager, 41
- defTemperature
  - chain::ChainManager, 41
- delCommand
  - plot::PlotManager, 83
- delModelString
  - xset::XspecSettings, 104
- delta
  - fit::FitManager, 59
- device
  - plot::PlotManager, 86



- diagrsp
  - data::DataManager, 45
- dof
  - fit::FitManager, 60
- dummyrsp
  - data::DataManager, 45
  - spectrum::Spectrum, 95
- energies
  - model::Model, 64
  - response::Response, 90
  - spectrum::Spectrum, 98
- eqwidth
  - model::ModelManager, 71
  - spectrum::Spectrum, 98
- error
  - fit::FitManager, 56
  - model::Parameter, 77
- exposure
  - data::FakeitSettings, 52
  - spectrum::Background, 33
  - spectrum::Spectrum, 98
- fakeit
  - data::DataManager, 46
- fileName
  - chain::Chain, 36
  - data::FakeitSettings, 53
  - spectrum::Background, 33
  - spectrum::Spectrum, 98
- fileType
  - chain::Chain, 36
- fit::FitManager, 53
  - \_\_init\_\_, 56
  - bayes, 59
  - criticalDelta, 59
  - delta, 59
  - dof, 60
  - error, 56
  - ftest, 57
  - goodness, 57
  - improve, 57
  - method, 60
  - nIterations, 60
  - perform, 58
  - query, 60
  - renorm, 58
  - show, 58
  - statistic, 61
  - statMethod, 61
  - steppar, 58
  - weight, 61
- flux
  - model::Model, 67
  - spectrum::Spectrum, 99
- folded
  - model::Model, 65
- frozen
  - model::Parameter, 77
- ftest
  - fit::FitManager, 57
- goodness
  - fit::FitManager, 57
- ignore
  - data::DataManager, 48
  - spectrum::Spectrum, 95
- improve
  - fit::FitManager, 57
- index
  - spectrum::Spectrum, 99
- initpackage
  - model::ModelManager, 71
- iplot
  - plot::PlotManager, 83
- isPoisson
  - spectrum::Background, 33
  - spectrum::Spectrum, 99
- link
  - model::Parameter, 78
- lmod
  - model::ModelManager, 72
- log
  - xset::XspecSettings, 106
- logChatter
  - xset::XspecSettings, 106
- lumin
  - model::Model, 67
  - spectrum::Spectrum, 99
- method

- fit::FitManager, 60
- model
  - plot::PlotManager, 83
  - model::Component, 42
    - \_\_init\_\_, 42
    - \_\_setattr\_\_, 43
    - name, 43
    - parameterNames, 43
  - model::Model, 61
    - \_\_call\_\_, 64
    - \_\_init\_\_, 63
    - \_\_setattr\_\_, 64
    - componentNames, 67
    - energies, 64
    - flux, 67
    - folded, 65
    - lumin, 67
    - name, 67
    - nParameters, 67
    - setPars, 65
    - show, 66
    - showList, 66
    - startParIndex, 68
    - untie, 66
    - values, 66
  - model::ModelManager, 68
    - \_\_call\_\_, 69
    - \_\_iadd\_\_, 69
    - \_\_init\_\_, 69
    - \_\_isub\_\_, 70
    - calcFlux, 70
    - calcLumin, 70
    - clear, 70
    - eqwidth, 71
    - initpackage, 71
    - lmod, 72
    - setEnergies, 72
    - show, 73
    - systematic, 74
  - model::Parameter, 74
    - \_\_add\_\_, 76
    - \_\_float\_\_, 76
    - \_\_iadd\_\_, 76
    - \_\_imul\_\_, 77
    - \_\_init\_\_, 76
    - \_\_mul\_\_, 77
    - \_\_radd\_\_, 77
    - \_\_rmul\_\_, 77
    - error, 77
    - frozen, 77
    - link, 78
    - name, 78
    - prior, 78
    - sigma, 78
    - unit, 78
    - untie, 77
    - values, 78
  - modelStrings
    - xset::XspecSettings, 106
  - multiresponse
    - spectrum::Spectrum, 99
  - name
    - model::Component, 43
    - model::Model, 67
    - model::Parameter, 78
  - nGroups
    - data::DataManager, 49
  - nIterations
    - fit::FitManager, 60
  - noID
    - plot::PlotManager, 83
  - notice
    - data::DataManager, 48
    - spectrum::Spectrum, 96
  - noticed
    - spectrum::Spectrum, 100
  - noticedString
    - spectrum::Spectrum, 96
  - nParameters
    - model::Model, 67
  - nSpectra
    - data::DataManager, 49
  - openLog
    - xset::XspecSettings, 104
  - parameterNames
    - model::Component, 43
  - perform
    - fit::FitManager, 58
  - perHz

- plot::PlotManager, 86
- plot::PlotManager, 79
  - \_\_call\_\_, 82
  - \_\_init\_\_, 82
  - add, 86
  - addCommand, 82
  - area, 86
  - background, 86
  - backgroundVals, 82
  - commands, 86
  - delCommand, 83
  - device, 86
  - iplot, 83
  - model, 83
  - noID, 83
  - perHz, 86
  - redshift, 87
  - setGroup, 83
  - setID, 84
  - setRebin, 84
  - show, 85
  - splashPage, 87
  - x, 85
  - xAxis, 87
  - xErr, 85
  - xLog, 87
  - y, 85
  - yErr, 85
  - yLog, 88
- prior
  - model::Parameter, 78
- proposal
  - chain::Chain, 36
- query
  - fit::FitManager, 60
- rand
  - chain::Chain, 37
- rate
  - spectrum::Spectrum, 100
- redshift
  - plot::PlotManager, 87
- removeDummyrsp
  - data::DataManager, 49
- renorm
  - fit::FitManager, 58
- response
  - data::FakeitSettings, 53
  - spectrum::Spectrum, 100
- response::Response, 88
  - \_\_init\_\_, 89
  - arf, 89
  - chanEnergies, 89
  - energies, 90
  - rmf, 90
  - sourceNumber, 90
- rmf
  - response::Response, 90
- run
  - chain::Chain, 36
- runLength
  - chain::Chain, 37
- seed
  - xset::XspecSettings, 107
- setEnergies
  - model::ModelManager, 72
- setGroup
  - plot::PlotManager, 83
- setID
  - plot::PlotManager, 84
- setPars
  - model::Model, 65
- setRebin
  - plot::PlotManager, 84
- show
  - chain::Chain, 36
  - chain::ChainManager, 40
  - data::DataManager, 49
  - fit::FitManager, 58
  - model::Model, 66
  - model::ModelManager, 73
  - plot::PlotManager, 85
  - spectrum::Spectrum, 96
  - xset::XspecSettings, 105
- showList
  - model::Model, 66
- sigma
  - model::Parameter, 78
- sourceNumber
  - response::Response, 90

- spectrum::Background, 31
  - \_\_init\_\_, 32
  - areaScale, 33
  - exposure, 33
  - fileName, 33
  - isPoisson, 33
  - values, 33
  - variance, 33
- spectrum::Spectrum, 90
  - \_\_init\_\_, 94
  - areaScale, 97
  - background, 97
  - cornorm, 97
  - correction, 97
  - dataGroup, 98
  - dummyrsp, 95
  - energies, 98
  - eqwidth, 98
  - exposure, 98
  - fileName, 98
  - flux, 99
  - ignore, 95
  - index, 99
  - isPoisson, 99
  - lumin, 99
  - multiresponse, 99
  - notice, 96
  - noticed, 100
  - noticedString, 96
  - rate, 100
  - response, 100
  - show, 96
  - values, 101
  - variance, 101
- splashPage
  - plot::PlotManager, 87
- startParIndex
  - model::Model, 68
- stat
  - chain::ChainManager, 40
- statistic
  - fit::FitManager, 61
- statMethod
  - fit::FitManager, 61
- steppar
  - fit::FitManager, 58
- systematic
  - model::ModelManager, 74
- temperature
  - chain::Chain, 37
- totalLength
  - chain::Chain, 37
- unit
  - model::Parameter, 78
- untie
  - model::Model, 66
  - model::Parameter, 77
- values
  - model::Model, 66
  - model::Parameter, 78
  - spectrum::Background, 33
  - spectrum::Spectrum, 101
- variance
  - spectrum::Background, 33
  - spectrum::Spectrum, 101
- version
  - xset::XspecSettings, 107
- weight
  - fit::FitManager, 61
- x
  - plot::PlotManager, 85
- xAxis
  - plot::PlotManager, 87
- xErr
  - plot::PlotManager, 85
- xLog
  - plot::PlotManager, 87
- xsect
  - xset::XspecSettings, 107
- xset::XspecSettings, 101
  - \_\_init\_\_, 104
  - abund, 105
  - addModelString, 104
  - allowNewAttributes, 105
  - chatter, 105
  - closeLog, 104
  - cosmo, 105
  - delModelString, 104

log, [106](#)  
logChatter, [106](#)  
modelStrings, [106](#)  
openLog, [104](#)  
seed, [107](#)  
show, [105](#)  
version, [107](#)  
xsect, [107](#)

y  
    plot::PlotManager, [85](#)  
yErr  
    plot::PlotManager, [85](#)  
yLog  
    plot::PlotManager, [88](#)