

Anatomy of a XRISM Simulation

Originally presented at XRISM Science Team Meeting JAXA/ISAS, May 2019

Updated June 2019

Where and How to Get Stuff



- Go to XRISM SDC Tools Pre-launch Builds website on confluence/XARM_INTL
<https://galaxy.astro.isas.jaxa.jp/confluence/display/XINTL/XRISM+SDC+Tools+Pre-launch+Builds>
- “README”s lead to
<ftp://legacy.gsfc.nasa.gov/xrism/prelaunch/simulation/sim2/>
- Download tarfiles and User Guide “heasim_20170825.pdf”

Spectral Simulations: The Basics



- This suite of files (in `specfiles_v002.tar.gz`) is sufficient to assess feasibility (for a given exposure time) of meeting the spectral goals of most prospective XRISM targets. See `README_XRISM_SPECFILES.txt` for details.
- The files are in-flight hitomi sxs response files (renamed to “resolve”).
- Spectral simulations in the standard way, e.g. XSPEC/fakeit (User Guide SB.1).
- Normalized response matrix (RMF) files that include only the Gaussian core of the line spread function (LSF) are provided, for 4 (constant) values of FWHM:
 `resolve_h5ev_2019a.rmf` `resolve_h7ev_2019a.rmf`
 `resolve_m6ev_2019a.rmf` `resolve_m8ev_2019a.rmf`
- Note: NXB generally negligible (~ 0.01 c/s/array), but files corresponding to each of the 4 RMFs described above are now provided.

Spectral Simulations: Effective Area



Six “ARF”s that convert flux to 0.11-25 keV counts over the full calorimeter array, either with gate-valve open (“noGV”) or closed (“withGV”), are provided.

- Includes the (Hitomi SXS) quantum efficiency, optical blocking filter transmission.

name	spatial distribution
resolve_pnt_spec_noGV_20190611.arf	on-axis point source, gatevalve open
resolve_pnt_spec_withGV_20190611.arf	on-axis point source, gatevalve closed
resolve_flt_spec_noGV_20190611.arf	5 arcmin radius uniform circle centered on-axis, gatevalve open
resolve_flt_spec_withGV_20190611.arf	5 arcmin radius uniform circle centered on-axis, gatevalve closed
resolve_bet_spec_noGV_20190611.arf	5.7 arcmin radius beta-model, beta=0.57, 1.26 arcmin core centered on-axis, gatevalve open
resolve_bet_spec_withGV_20190611.arf	5.7 arcmin radius beta-model, beta=0.57, 1.26 arcmin core centered on-axis, gatevalve closed

For a general extended source, the point source arf should be good to ~25% in converting flux from a small (<array) region to a count rate – when in doubt use that one, or do a full simulation (see below).

Full Simulation: Setup



- (1) Follow the instructions to setup and install XRISM_05Dec2018_Build1.
- (2) Download and unpack support files and sample scripts:
`tar -xvzf heasimfiles_20190619.tar.gz`
`tar -xvzf heasimscripts_20170830.tar.gz`
- (3) Set the HEASIM_SUPPORT environment variable:
`setenv HEASIM_SUPPORT <heasimfilesdir> (C-shell) or`
`export XSELECT_MDB=<heasimfilesdir> (Bash) – typo in guide here`
- (4) Set the XSELECT_MDB environment variable to run *xselect* on your output:
`setenv XSELECT_MDB $HEASIM_SUPPORT/auxiliary/xselect.mdb.heasim (C-shell) or`
`export XSELECT_MDB=$HEASIM_SUPPORT/auxiliary/xselect.mdb.heasim (Bash)`

Anatomy of a XRISM “Perseus” Simulation

Step 1: Make Xspec qdp Model Files

In this example “Perseus” = beta model ICM (TBabs*bvvapec) plus point source AGN (Tbabs*plaw)

```
XSPEC12>@perseus_icm_abs_mod.xcm
```

```
XSPEC12>data none
```

```
XSPEC12>energ 0.1 27.1 27000
```

```
XSPEC12>cpd /xs
```

```
XSPEC12>setplot comm wdata perseus_icm_abs_mod.qdp
```

```
XSPEC12>plot model
```

```
XSPEC12>@perseus_brtpsrc_mod.xcm
```


```
XSPEC12>data none
```

```
XSPEC12>energ 0.1 27.1 27000
```

```
XSPEC12>cpd /xs
```

```
XSPEC12>setplot comm wdata perseus_brtpsrc_mod.qdp
```


```
XSPEC12>plot model
```



energy range spans the instrument band
energy bin smaller than instrument resolution.

Model should be properly normalized
(i.e., give the correct flux).

Combine all components with the same
spatial distribution into one model.



Step 2: Make source definition files

perseus_betaicm.dat ==

49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_icm_abs_mod.qdp,2,2,extmod(beta,0.53,1.26,1.0,0.0,0.0,5.7)

49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_brtpsrc_mod.qdp,2,2

RA,DEC,NH,spectrum,flux,bandpass,specfile,specunits,specformat,source_specifications

RA,DEC	source coordinates.
NH	column density: set to 0 if absorption is included in the input spectrum.
spectrum	“user” if using input spectrum.
flux	source flux in erg/sec/cm ² : set to 0 if using an input spectrum (flux is calculated from that).
bandpass	bandpass within which flux is calculated: set to 0.0-0.0 if using an input spectrum.
specfile	qdp file name: see guide for other formats.
specunits	2 for specfile derived as shown: see guide for other options tied to specfile.
specformat	2 for specfile derived as shown: see guide for other options tied to specfile.
source_specs	extended spatial distribution, or time variation, specifier (if any) Here, a beta=0.53, core radius =1.26 arcmin beta-model extending to 5.7 arcmin. The specified flux corresponds to this distribution.

Step 3: Run the (on-axis) Simulations



```
heasim mission=hitomi instrume=sxs rapoint=49.95 decpoint=41.51 roll=0.00 exposure=200000.  
insrcdeffile=perseus_betaicm_brptsrc.dat outfile=perseus_betaicm_brptsrc.fits  
psffile=$HEASIM_SUPPORT/hitomi/sxs/psf/eef_from_sxs_psfimage_20140618.fits  
vigfile=$HEASIM_SUPPORT/hitomi/sxs/vignette/SXT_VIG_140618.txt  
rmffile=$HEASIM_SUPPORT/hitomi/sxs/response/resolve_h5ev_2019a.rmf  
arffile=$HEASIM_SUPPORT/hitomi/sxs/response/resolve_pnt_heasim_noGV_20190611.arf  
intbackfile=none flagsubex=no seed=1234567890 clobber=yes
```

NOTE: We (now) recommend using a single point source arf and including vignetting.


Step 5: Extract and Fit the Spectra

Spectra may be extracted using `xselect` within the `HEASIM_SUPPORT` environment, and fit using `Xspec`.

```
XSPEC12>data 1:1 perseus_betaicm_brptsrc_merged_sorted.pi
XSPEC12>response 1:1 resolve_h5ev_2019a.rmf
XSPEC12>response 2:1 resolve_h5ev_2019a.rmf
XSPEC12>arf 1:1 resolve_bet_spec_noGV_20190611.arf
XSPEC12>arf 2:1 resolve_pnt_spec_noGV_20190611.arf
XSPEC12>model TBabs*bvvapec
XSPEC12>... specify params
XSPEC12>model 2:agn constant*TBabs*powerlaw
XSPEC12>... specify params
```

Note: Different ARFs from that used as heasim input.

Note: Count rate is “correct”; use appropriate extended source ARF to recover input flux.




You may wish to... Use an Image

```
perseus_imageicm.dat == 49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_icm_abs_mod.qdp,  
2,2,image(acis_chip0_band1_norm.img,0,0,0,0)
```

```
heasim mission=hitomi instrume=sxs rapoint=49.95 decpoint=41.51 roll=0.00 exposure=200000.  
insrcdeffile=perseus_imageicm.dat outfile=perseus_imageicm.fits psffile=$HEASIM_SUPPORT/hitomi/sxs/psf/  
eef_from_sxs_psfimage_20140618.fits vigfile=$HEASIM_SUPPORT/hitomi/sxs/vignette/SXT_VIG_140618.txt  
rmffile=$HEASIM_SUPPORT/hitomi/sxs/response/resolve_h5ev_2019a.rmfile=$HEASIM_SUPPORT/hitomi/sxs/  
response/resolve_pnt_heasim_noGV_20190611.arf intbackfile=none flagsubex=no seed=1234567890 clobber=yes
```

sxs_psfimage_20140618.fits



You may wish to... Add a line

perseus_betaicm_brptsrc_line.dat ==

49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_icm_abs_mod.qdp,2,2,extmod(beta,0.53,1.26,1.0,0.0,0.0,5.7)


49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_brptsrc_mod.qdp,2,2

49.95,41.51,0.0,**mono,3.5**,1.0e-13,2.5-4.5,none,2,2,**extmod(beta,0.66,0.1,1.0,0.0,0.0,5.7)**

heasim mission=hitomi instrume=sxs rapoint=49.95 decpoint=41.51 roll=0.00 exposure=200000.

insrcdeffile=**perseus_betaicm_brptsrc_line.dat** outfile=perseus_betaicm_brptsrc_line.fits...

mono: narrow gaussian line
For finite width use user model



You may wish to... Use a FW ARF

```
heasim mission=astro-h instrume=sxs rapoint=49.95 decpoint=41.51 roll=0.00 exposure=200000.  
insrcdeffile=perseus_betaicm_brptsrc.dat outfile=perseus_betaicm_brptsrc.fits psffile=$HEASIM_SUPPORT/  
astro-h/sxs/psf/eef_from_sxs_psfimage_20140618.fits vigfile=$HEASIM_SUPPORT/astro-h/sxs/vignette/  
SXT_VIG_140618.txt rmffile=$HEASIM_SUPPORT/astro-h/sxs/response/ah_sxs_5ev_20130806.rmf  
arffile=$HEASIM_SUPPORT/astro-h/sxs/response/sxt s_140505_ts02um_Be_intall_140618psf.arf  
intbackfile=none flagsubex=no seed=1234567890 clobber=yes
```

In Xspec, use **ah_sxs_5ev_20130806.rmf, sxt-s_140505_ts02um_Be_intallpxl.arf**

```
heasim mission=astro-h instrume=sxs rapoint=49.95 decpoint=41.51 roll=0.00 exposure=200000.  
insrcdeffile=perseus_betaicm_brptsrc.dat outfile=perseus_betaicm_brptsrc.fits psffile=$HEASIM_SUPPORT/  
astro-h/sxs/psf/eef_from_sxs_psfimage_20140618.fits vigfile=$HEASIM_SUPPORT/astro-h/sxs/vignette/  
SXT_VIG_140618.txt rmffile=$HEASIM_SUPPORT/astro-h/sxs/response/ah_sxs_5ev_20130806.rmf  
arffile=$HEASIM_SUPPORT/astro-h/sxs/response/sxt s_140505_ts02um_ND_intall_140618psf.arf  
intbackfile=none flagsubex=no seed=1234567890 clobber=yes
```

In Xspec, use **ah_sxs_5ev_20130806.rmf, sxt-s_140505_ts02um_ND_intallpxl.arf**

```
heasim mission=astro-h instrume=sxs rapoint=49.95 decpoint=41.51 roll=0.00 exposure=200000.  
insrcdeffile=perseus_betaicm_brptsrc.dat outfile=perseus_betaicm_brptsrc.fits psffile=$HEASIM_SUPPORT/  
astro-h/sxs/psf/eef_from_sxs_psfimage_20140618.fits vigfile=$HEASIM_SUPPORT/astro-h/sxs/vignette/  
SXT_VIG_140618.txt rmffile=$HEASIM_SUPPORT/astro-h/sxs/response/ah_sxs_5ev_20130806.rmf  
arffile=$HEASIM_SUPPORT/astro-h/sxs/response/sxt s_140505_ts02um_CBF_intall_140618psf.arf  
intbackfile=none flagsubex=no seed=1234567890 clobber=yes
```

In Xspec, use **ah_sxs_5ev_20130806.rmf, sxt-s_140505_ts02um_CBF_intallpxl.arf**

You may wish to... Filter events

- Use HP and MP for hi-rez spectroscopy.
- Rule of thumb: check branching if >1 ct/sec/pixel.

sxsbranch

- computes branching ratios for each event resolution grade -- for each pixel, and over the entire array
- statistically estimates these quantities using Poisson statistics, based on some count distribution in pixels
- produces a more realistic version of the event file by populating the **PIXEL**, and **ITYPE** columns with the grade (ITYPE = 0:HP, 1:MP, 2:MS, 3:LP, 4:LS)

```
sxsbranch infile=perseus_betaicm_brptsrc.fits filetype=sim  
outfile=perseus_betaicm_brptsrc_branch.out pixfrac=$HEASIM_SUPPORT/astro-h/sxsbranch/  
pixfrac.txt pixmask=none
```

For example, in Xselect...

- xsel:HITOMI-SXS-PX_NORMAL > read events **perseus_betaicm_brptsrc.fits.out**
- xsel:HITOMI-SXS-PX_NORMAL > filter column "PIXEL=27:35" *corner of the array*
- xsel:HITOMI-SXS-PX_NORMAL > filter GRADE "0:1" HP only (1:MP, 2:MS, 3:LP, 4:LS)

DOs, DON'Ts and Takeaways



- DO install XRISM build 1 and the simulation support files.
- For isolated point sources, Xspec sim is sufficient – but DO run *sxsbranch* if the source is bright.
- DO use Xspec to create input spectra for your simulation.
- DO take advantage of the multi-component source capabilities of heasim and Xspec.
- For Resolve, one DOES NOT need the source to extend beyond ~6 arcmin.
- DO use the point source ARF with vignetting for extended sources to get the most accurate count rate. But...
- DO be mindful of norms for extended sources (use the correct ARF in Xspec to get the right flux).
- For Resolve, the NXB is negligible for most cases
- Please DO direct all questions, concerns, requests to...

XRISM-SDC-help@lists.nasa.gov (there's a form!).