

XRISM simulations using heasim – quick guide for the XRISM Science Team

(1) Where and how to retrieve files and docs

Links and README files are available on the XRISM SDC Tools Pre-launch Builds website on confluence/XARM_INTL,

<https://galaxy.astro.isas.jaxa.jp/confluence/display/XINTL/XRISM+SDC+Tools+Pre-launch+Builds>

The READMEs direct users to

<https://heasarc.gsfc.nasa.gov/FTP/xrism/prelaunch/simulation/sim3/>

from where the necessary tarfiles are located along with additional guiding documents.

(2) Spectral Simulations

This suite of available files (in specfiles_v003.tar.gz) is sufficient to assess feasibility (for a given exposure time) of meeting the spectral goals of most prospective XRISM targets (see README_XRISM_SPECFILES.txt for details). The files are in-flight hitomi sxs (renamed to “resolve”) response and non-X-ray background (NXB) files, as well as pre-flight hitomi sxi (renamed to “xtend”) response and background files. The NXB is negligible for bright point sources.

Spectral simulations may be conducted in the standard way, e.g. XSPEC/fakeit (see Section B.1 of heasim_20170825.pdf, available at the website mentioned above). The table below lists and describes the available files.

The (normalized) Resolve response matrix files (RMF) include only the Gaussian core of the line spread function (LSF) and are provided for four different values of the FWHM – as are the corresponding Resolve NXB spectra. Provisionally, the 5 and 6 (7 and 8) eV files correspond to high- and mid-resolution events in the nominal (requirement-satisfying) case. The Resolve effective area (ARF) files include the quantum efficiency and the dewar filter stack optical blocking filter transmission. They range over energies 0.11-25 keV and include gate-valve open (“noGV”) and closed (“withGV”) versions. Note that the above ARFs were made with the new gate valve model (the CalDB file for which is included in the XRISM Build 3 CalDB release). The gate valve for XRISM has a different structure compared to the Hitomi one, which impacts the effective area. In addition to these Filter Wheel Open files, ARFs for Beryllium filter (“BeFw”) and Neutral density (“ND”) filter selections are provided (the gate valve is assumed open in these cases). Resolve NXB spectra are based on Hitomi pre-launch estimates with the addition of MnK-alpha and K-beta features with fluxes estimated by the instrument team. These

are consistent with in-flight Hitomi SXS NXB spectra derived using the 'sxsnxbgen' ftool. The Resolve NXB, at ~ 0.01 ct/s over the Resolve array, is negligible in most cases of interest.

The Hitomi (Astro-H) pre-launch Xtend ARF, RMF, and NXB spectral files were derived using a 1.8 arcminute radius circular extraction region. The NXB spectrum for the entire FoV ("full") is also included.

FILE	NOTE
Resolve	
resolve_h5ev_2019a.rmf	High resolution, nominal
resolve_m6ev_2019a.rmf	Mid resolution, nominal
resolve_h7ev_2019a.rmf	High resolution, required
resolve_m8ev_2019a.rmf	Mid resolution, required
resolve_pnt_spec_noGV_20190701.arf	On-axis point source, gatevalve open
resolve_pnt_spec_withGV_20190701.arf	On-axis point source, gatevalve closed
resolve_bet_spec_noGV_20190611.arf	5.7 arcmin radius beta-model, $\beta=0.57$, 1.26 arcmin core centered on-axis, gatevalve open
resolve_bet_spec_withGV_20190611.arf	5.7 arcmin radius beta-model, $\beta=0.57$, 1.26 arcmin core centered on-axis, gatevalve closed
resolve_flt_spec_noGV_20190611.arf	5 arcmin radius uniform circle centered on-axis, gatevalve open
resolve_flt_spec_withGV_20190611.arf	5 arcmin radius uniform circle centered on-axis, gatevalve closed
resolve_pnt_spec_BeFw_20190701.arf	On-axis point source, Be filter
resolve_pnt_spec_ND_20190701.arf	On-axis point source, Neutral Density filter
resolve_h5ev_2019a_rslnxb.pha	Use with resolve_h5ev_2019a.rmf
resolve_m6ev_2019a_rslnxb.pha	Use with resolve_m6ev_2019a.rmf
resolve_h7ev_2019a_rslnxb.pha	Use with resolve_h7ev_2019a.rmf
resolve_m8ev_2019a_rslnxb.pha	Use with resolve_m8ev_2019a.rmf
Xtend	
ah_sxi_20120702.rmf	SXI pre-launch
sxt-i_140505_ts02um_int01.8r.arf	1.8 arcminute radius circular extraction region
ah_sxi_pch_nxb_r1p80_20110530.pi	Use with sxt-i_140505_ts02um_int01.8r.arf
ah_sxi_pch_nxb_full_20110530.pi	Full field-of-view

As a rule of thumb, even for an extended source, the point source arf should be good to $\sim 25\%$ in converting flux from a small ($< \text{array}$) region to a count rate. Do a full simulation (see below) for somewhat more accurate treatment of off-axis and extended sources.


(3) Simulating the Perseus Cluster with Heasim – A Worked Example

In order to run heasim, HEASoft (or XRISM Build 3) needs to be installed and initialized. The Hitomi CalDB must also be installed and initialized if one wishes to assign pixels and grades to heasim event files using the sxsbranch ftool (see below).

(a) Step 1: Make Xspec qdp model files representing the spectrum of each spatial component


Absorbed thermal (ICM) component model “perseus_icm_abs_mod.xcm” –

```
XSPEC12>@perseus_icm_abs_mod.xcm
XSPEC12>data none
XSPEC12>energ 0.1 27.1 27000
XSPEC12>cpd /xs
XSPEC12>setplot comm wdata perseus_icm_abs_mod.qdp
XSPEC12>plot model
```



Absorbed non-thermal (AGN) component model “perseus_brtpssrc_mod.xcm” –

```
XSPEC12>@perseus_brtpssrc_mod.xcm
XSPEC12>data none
XSPEC12>energ 0.1 27.1 27000
XSPEC12>cpd /xs
XSPEC12>setplot comm wdata perseus_brtpssrc_mod.qdp
XSPEC12>plot model
```



Tips –

- Set the energy range in the Xspec *energ* command to span the instrument bandpass.
- Set the energy bin size in the Xspec *energ* command to be smaller than the instrument resolution.
- Properly normalize the model so that it yields the correct flux over the extent of the spatial model (see below).
- Combine all components with the same spatial distribution into one spectral model, if possible.

(b) Step 2: Create the source definition file

Heasim requires a source definition file (“sdf”) as input to specify the source position in the sky, and source characteristics (consult [heasim_20170825.pdf](#) for additional details). Each line represents a single source, or single component of a multi-component source. The comma-separated elements of the sdf are as follows:

RA,DEC,NH,spectrum,flux,bandpass,specfile,specunits,specformat,source_specifications

For our Perseus simulation, the sdf representing the extended thermal, and point-like non-thermal, components is as follows:

```
perseus_betaicm.dat ==
49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_icm_abs_mod.qdp,2,2,extmod(beta,0.53,1.26,1.0,0.0,0.0,5.7)
49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_brtpsrc_mod.qdp,2,2
```

RA,DEC	Source coordinates.
NH	Column density: set to 0 if absorption is included in the input spectrum.
spectrum	Set to “user” if using input spectrum.
flux	Source flux in erg/sec/cm2: set to 0 if using an input spectrum (flux will be calculated from that).

bandpass	Bandpass within which flux is calculated: set to 0.0-0.0 if using an input spectrum.
specfile	File name of input spectrum (qdp) file name: see guide for other formats.
specunits	2 for specfile derived as shown: see guide for other options tied to specfile.
specformat	2 for specfile derived as shown: see guide for other options tied to specfile.
source_specifications	Extended spatial distribution, or time variation, specifier (if any). Here, a $\beta=0.53$, core radius = 1.26 arcmin β -model extending to 5.7 arcmin is adopted for the Perseus ICM. The specified flux corresponds to this distribution.

(c) Step 3: Simulation setup

The heasim support files may be installed as follows:

- 1) Download and unpack support files `heasimfiles_20201012.tar.gz`, placing them in some directory `<heasimfilesdir>`
- 2) Set the `HEASIM_SUPPORT` environment variable:

```
setenv HEASIM_SUPPORT <heasimfilesdir> (C-shell) or
export XSELECT_MDB=<heasimfilesdir> (Bash)
```

(d) Step 4: Run the simulation

The heasim command to run the Perseus Cluster simulation (200 ks exposure) is given below. Since the pointing RA and DEC are the same as those for the source, an on-axis simulation is conducted. For point sources, the vignetting function may be ignored (“`vigfile=none`”). As mentioned above, the NXB may be neglected in most cases (“`intbackfile=none`”), but is included here for demonstration purposes. Note that the input ARF file is not the same as that used for spectral simulations, since heasim must account for photons originating outside of the field-of-view. In the simulation below, the psffile is specified as an eef and thus results in an axisymmetric X-ray distribution. The image file `sxs_psfimage_20140618.fits` may instead be used to include the effects of PSF asymmetries.

```
heasim mission=hitomi instrume=sxs rapoint=49.95 decpoint=41.51 roll=0.00 exposure=200000.
insrcdeffile=perseus_betaicm_brptsrc.dat outfile=perseus_betaicm_brptsrc.fits
psffile=$HEASIM_SUPPORT/xrism/resolve/psf/eef_from_sxs_psfimage_20140618.fits
vigfile=$HEASIM_SUPPORT/xrism/resolve/vignette/SXT_VIG_140618.txt
rmffile=$HEASIM_SUPPORT/xrism/resolve/response/resolve_h5ev_2019a.rmf
arffile=$HEASIM_SUPPORT/xrism/resolve/response/resolve_pnt_heasim_noGV_20190701.arf
intbackfile=$HEASIM_SUPPORT/xrism/resolve/background/resolve_h5ev_2019a_rslxb.pha
flagsubex=no seed=1234567890 clobber=yes
```

(e) Step 5: Extract and analyze the Resolve spectrum

- 1) Set the `XSELECT_MDB` environment variable to run xselect on your output:

```
setenv XSELECT_MDB $HEASIM_SUPPORT/xrism/auxiliary/xselect.mdb.heasim
(C-shell) or
export XSELECT_MDB=$HEASIM_SUPPORT/xrism/auxiliary/xselect.mdb.heasim
(Bash)
```


- 2) Extract the spectrum from the heasim output file using xselect:

```
xsel:HITOMI-SXS-PX_NORMAL > read events perseus_betaicm_brptsrc.fits
xsel:HITOMI-SXS-PX_NORMAL > extract spectrum
xsel:HITOMI-SXS-PX_NORMAL > save spectrum perseus_betaicm_brptsrc.pi
```

- 3) Analyze the spectrum.

```
XSPEC12>data 1:1 perseus_betaicm_brptsrc.pi
XSPEC12>response 1:1 resolve_h5ev_2019a.rmf
XSPEC12>response 2:1 resolve_h5ev_2019a.rmf
XSPEC12>arf 1:1 resolve_bet_spec_noGV_20190611.arf
XSPEC12>arf 2:1 resolve_pnt_spec_noGV_20190701.arf
XSPEC12>model TBabs*bvvapec
XSPEC12>... specify params
XSPEC12>model 2:agn constant*TBabs*powerlaw
XSPEC12>... specify params
XSPEC12>... fit, derive errors, etc.
```

The above spectrum is compared to its generating model, and its components, below. Note that different ARFs from that used as heasim input are applied in spectral fitting. The extended source ARF, `resolve_bet_spec_noGV_20190611.arf`, is exclusively appropriate to the simulation at hand. More generally, one may use the point source ARF for both components to recover the spectral parameters and uncertainties, however the flux of the extended component will not be correct (expert users may generate the appropriate extended source ARF to recover input flux).




(4) Simulating The Perseus Cluster with heasim – variations

(a) Use an input image, rather than a spatial model

In this case the source definition file is

```
insrcdeffile=perseus_imageicm.dat ==  
49.95,41.51,0.0,user,0.,0.,0.0.,perseus_icm_abs_mod.qdp,2,2,image(acis_chip0_band1_norm.img,0,0,0,0)
```

and, otherwise, the command may be issued as before. The output and input images are shown below.




(b) Include an additional component - in this case a narrow 3.5 keV emission line

In this case the source definition file is

```
insrcdeffile=perseus_betaicm_brptsrc_line.dat ==  
49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_icm_abs_mod.qdp,2,2,extmod(beta,0.53,1.26,1.0,0.0,0.0,5.7)  
49.95,41.51,0.0,user,0.,0.,0.-0.,perseus_brptsrc_mod.qdp,2,2  
49.95,41.51,0.0,mono,3.5,1.0e-13,2.5-4.5,none,2,2,extmod(beta,0.66,0.1,1.0,0.0,0.0,5.7)
```

and, otherwise, the command may be issued as before. The spectrum and original (without the extra line) model are shown below. The “mono” model corresponds to a zero-width gaussian line; for finite width use user model.



(c) Simulate a source observed using one of the filter wheel filters

For the Be filter that preferentially reduces the low energy through, set

```
arffile=$HEASIM_SUPPORT/xrism/resolve/response/resolve_pnt_heasim_BeFw_20190701.arf
```

and, otherwise, issue the command as before. In analyzing the spectrum extracted from the simulated event file, use `resolve_pnt_spec_BeFw_20190701.arf`.

Similarly, for the neutral density filter, set

```
arffile=$HEASIM_SUPPORT/xrism/resolve/response/resolve_pnt_heasim_ND_20190701.arf
```

and, otherwise, issue the command as before. In analyzing the spectrum extracted from the simulated event file, use `resolve_pnt_spec_ND_20190701.arf`.

(d) Filter the simulated event file on, e.g., pixel or resolution grade

For the highest quality spectroscopy, only Resolve high- and mid-resolution grade events are most useful. The `sxsbranch` ftool calculates the grade branching ratios for each pixel, and over the entire array, and creates an enhanced simulation event file with `PIXEL` and `IYTPE` (grade; `ITYPE` = 0:HP, 1:MP, 2:MS, 3:LP, 4:LS) columns. As a rule of thumb, one ought to check the branching ration is cases where the count rate per pixel exceeds 1 ct/sec/pixel. An example or the `sxsbranch` command is

```
sxsbranch infile=perseus_betaicm_brptsrc.fits filetype=sim
outfile=perseus_betaicm_brptsrc_branch.out
pixfrac=$HEASIM_SUPPORT/xrism/resolve/sxsbranch/pixfrac.txt pixmask=none
ctelpixfile=$HEASIM_SUPPORT/xrism/resolve/sxsbranch/pixmap.fits ctphafrac1=0.0
ctphafrac2=0.0
```


An example of the subsequent xselect commands that selects only HP events in one corner of the array is

```
xsel:HITOMI-SXS-PX_NORMAL > read events perseus_betaicm_brptsrc.fits.out
xsel:HITOMI-SXS-PX_NORMAL > filter column "PIXEL=27:35"
xsel:HITOMI-SXS-PX_NORMAL > filter GRADE "0:0"
xsel:HITOMI-SXS-PX_NORMAL > extract spectrum
xsel:HITOMI-SXS-PX_NORMAL > save spectrum perseus_betaicm_brptsrc_HPsub.pi
```

(5) Xtend simulations

An example of an Xtend simulation of the Perseus Cluster corresponding to the worked example described above is

```
heasim mission=hitomi instrume=sxi rapoint=49.95 decpoint=41.51 roll=0.00 exposure=200000.
insrcdefile=perseus_betaicm_brptsrc.dat outfile=perseus_betaicm_brptsrc_xtd.fits
psffile=$HEASIM_SUPPORT/xrism/xtend/psf/eef_from_sxi_psimage_20140618.fits
vigfile=$HEASIM_SUPPORT/xrism/xtend/vignette/SXT_VIG_140618.txt
rmffile=$HEASIM_SUPPORT/xrism/xtend/response/ah_sxi_20120702.rmf
arffile=$HEASIM_SUPPORT/xrism/xtend/response/sxt-i_140505_ts02um_int01.8r_intall_140618psf.arf
intbackfile=$HEASIM_SUPPORT/xrism/xtend/background/ah_sxi_pch_nxb_full_20110530.pi
flagsubex=no seed=1234567890 clobber=yes
```

The spectrum may be extracted using xselect as previously described, and should be fit using the sxt-i_140505_ts02um_int01.8r.arf ARF file, and the ah_sxi_pch_nxb_r1p80_20110530.pi NXB file.

(6) Final Remarks - DOs, DON'Ts and Takeaways

- For isolated point sources, a spectral simulation may be sufficient – but DO run sxsbranch if the source is bright.
- DO use Xspec to create input spectra for your simulation.
- DO take advantage of the multi-component source capabilities of heasim and Xspec.
- For Resolve, one DOESN'T need the source to extend beyond ~6 arcmin.
- DO use the point source ARF with vignetting for extended sources to get the most accurate count rate. But...
- DO be mindful of norms for extended sources (must use the correct ARF in Xspec to get a precisely correct flux).
- For Resolve, the NXB is negligible in most cases.
- Please consult the more complete guides for more detailed information.
- DO direct all questions, concerns, requests, etc. to XRISM-SDC-help@lists.nasa.gov.

